

Yocto Project Reference Manual



Richard Purdie, Linux Foundation
<richard.purdie@linuxfoundation.org>

by Richard Purdie
Copyright © 2010-2012 Linux Foundation

Permission is granted to copy, distribute and/or modify this document under the terms of the Creative Commons Attribution-Share Alike 2.0 UK: England & Wales [<http://creativecommons.org/licenses/by-sa/2.0/uk/>] as published by Creative Commons.

Note

Due to production processes, there could be differences between the Yocto Project documentation bundled in the release tarball and the Yocto Project Reference Manual [<http://www.yoctoproject.org/docs/1.3/poky-ref-manual/poky-ref-manual.html>] on the Yocto Project [<http://www.yoctoproject.org>] website. For the latest version of this manual, see the manual on the website.

Table of Contents

1. Introduction	1
1.1. Introduction	1
1.2. Documentation Overview	1
1.3. System Requirements	1
1.3.1. Supported Linux Distributions	1
1.3.2. Required Packages for the Host Development System	2
1.4. Obtaining the Yocto Project	4
1.5. Development Checkouts	4
2. Using the Yocto Project	6
2.1. Running a Build	6
2.1.1. Build Overview	6
2.1.2. Building an Image Using GPL Components	6
2.2. Installing and Using the Result	6
2.3. Debugging Build Failures	7
2.3.1. Task Failures	7
2.3.2. Running Specific Tasks	7
2.3.3. Dependency Graphs	7
2.3.4. General BitBake Problems	8
2.3.5. Building with No Dependencies	8
2.3.6. Variables	8
2.3.7. Recipe Logging Mechanisms	8
2.3.8. Other Tips	9
3. Technical Details	10
3.1. Yocto Project Components	10
3.1.1. BitBake	10
3.1.2. Metadata (Recipes)	11
3.1.3. Classes	11
3.1.4. Configuration	11
3.2. Shared State Cache	11
3.2.1. Overall Architecture	11
3.2.2. Checksums (Signatures)	12
3.2.3. Shared State	13
3.2.4. Tips and Tricks	14
3.3. x32	15
3.3.1. Support	15
3.3.2. Future Development and Limitations	16
3.3.3. Using x32 Right Now	16
3.4. Licenses	16
3.4.1. Tracking License Changes	17
3.4.2. Enabling Commercially Licensed Recipes	18
4. Migrating to a Newer Yocto Project Release	20
4.1. Moving to the Yocto Project 1.3 Release	20
4.1.1. Local Configuration	20
4.1.2. Recipes	20
5. Source Directory Structure	23
5.1. Top level core components	23
5.1.1. bitbake/	23
5.1.2. build/	23
5.1.3. documentation	23
5.1.4. meta/	23
5.1.5. meta-yocto/	23
5.1.6. meta-yocto-bsp/	24
5.1.7. meta-hob/	24
5.1.8. meta-skeleton/	24
5.1.9. scripts/	24
5.1.10. oe-init-build-env	24
5.1.11. LICENSE, README, and README.hardware	24
5.2. The Build Directory - build/	24
5.2.1. build/pseudodone	24
5.2.2. build/conf/local.conf	24
5.2.3. build/conf/bblayers.conf	25

5.2.4.	build/conf/sanity_info	25
5.2.5.	build/downloads/	25
5.2.6.	build/ssstate-cache/	25
5.2.7.	build/tmp/	25
5.2.8.	build/tmp/buildstats/	25
5.2.9.	build/tmp/cache/	25
5.2.10.	build/tmp/depoy/	25
5.2.11.	build/tmp/depoy/deb/	25
5.2.12.	build/tmp/depoy/rpm/	25
5.2.13.	build/tmp/depoy/licenses/	25
5.2.14.	build/tmp/depoy/images/	25
5.2.15.	build/tmp/depoy/ipk/	26
5.2.16.	build/tmp/sysroots/	26
5.2.17.	build/tmp/stamps/	26
5.2.18.	build/tmp/log/	26
5.2.19.	build/tmp/pkgdata/	26
5.2.20.	build/tmp/work/	26
5.3.	The Metadata - meta/	27
5.3.1.	meta/classes/	27
5.3.2.	meta/conf/	27
5.3.3.	meta/conf/machine/	27
5.3.4.	meta/conf/distro/	27
5.3.5.	meta/recipes-bsp/	27
5.3.6.	meta/recipes-connectivity/	27
5.3.7.	meta/recipes-core/	27
5.3.8.	meta/recipes-devtools/	27
5.3.9.	meta/recipes-extended/	27
5.3.10.	meta/recipes-gnome/	28
5.3.11.	meta/recipes-graphics/	28
5.3.12.	meta/recipes-kernel/	28
5.3.13.	meta/recipes-multimedia/	28
5.3.14.	meta/recipes-qt/	28
5.3.15.	meta/recipes-rt/	28
5.3.16.	meta/recipes-sato/	28
5.3.17.	meta/recipes-support/	28
5.3.18.	meta/site/	28
5.3.19.	meta/recipes.txt	28
6.	BitBake	29
6.1.	Parsing	29
6.2.	Preferences and Providers	29
6.3.	Dependencies	30
6.4.	The Task List	30
6.5.	Running a Task	30
6.6.	BitBake Command Line	31
6.7.	Fetchers	32
7.	Classes	33
7.1.	The base class - base.bbclass	33
7.2.	Autotooled Packages - autotools.bbclass	33
7.3.	Alternatives - update-alternatives.bbclass	33
7.4.	Initscripts - update-rc.d.bbclass	34
7.5.	Binary config scripts - binconfig.bbclass	34
7.6.	Debian renaming - debian.bbclass	34
7.7.	Pkg-config - pkgconfig.bbclass	34
7.8.	Distribution of sources - src_distribute_local.bbclass	34
7.9.	Perl modules - cpan.bbclass	34
7.10.	Python extensions - distutils.bbclass	35
7.11.	Developer Shell - devshell.bbclass	35
7.12.	Package Groups - packagegroup.bbclass	35
7.13.	Packaging - package*.bbclass	35
7.14.	Building kernels - kernel.bbclass	36
7.15.	Creating images - image.bbclass and rootfs*.bbclass	36
7.16.	Host System sanity checks - sanity.bbclass	36
7.17.	Generated output quality assurance checks - insane.bbclass	36
7.18.	Autotools configuration data cache - siteinfo.bbclass	37

7.19. Adding Users - useradd.bbclass	37
7.20. Using External Source - externalsrc.bbclass	37
7.21. Other Classes	38
8. Images	39
9. Reference: Features	41
9.1. Distro	41
9.2. Machine	41
9.3. Images	42
9.4. Feature Backfilling	42
10. Variables Glossary	44
11. Variable Context	70
11.1. Configuration	70
11.1.1. Distribution (Distro)	70
11.1.2. Machine	70
11.1.3. Local	70
11.2. Recipes	71
11.2.1. Required	71
11.2.2. Dependencies	71
11.2.3. Paths	71
11.2.4. Extra Build Information	71
12. FAQ	72
13. Contributing to the Yocto Project	77
13.1. Introduction	77
13.2. Tracking Bugs	77
13.3. Mailing lists	77
13.4. Internet Relay Chat (IRC)	77
13.5. Links	77
13.6. Contributions	78

Chapter 1. Introduction

1.1. Introduction

This manual provides reference information for the current release of the Yocto Project. The Yocto Project is an open-source collaboration project focused on embedded Linux developers. Amongst other things, the Yocto Project uses the OpenEmbedded build system, which is based on the Poky project, to construct complete Linux images. You can find complete introductory and getting started information on the Yocto Project by reading the Yocto Project Quick Start [<http://www.yoctoproject.org/docs/1.3/yocto-project-qs/yocto-project-qs.html>]. For task-based information using the Yocto Project, see the Yocto Project Development Manual [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html>]. You can also find lots of information on the Yocto Project on the Yocto Project website [<http://www.yoctoproject.org>].

1.2. Documentation Overview

This reference manual consists of the following:

- Using the Yocto Project: This chapter provides an overview of the components that make up the Yocto Project followed by information about debugging images created in the Yocto Project.
- Technical Details: This chapter describes fundamental Yocto Project components as well as an explanation behind how the Yocto Project uses shared state (sstate) cache to speed build time.
- Directory Structure: This chapter describes the source directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#source-directory>] created either by unpacking a released Yocto Project tarball on your host development system, or by cloning the upstream Poky [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#poky>] Git repository.
- BitBake: This chapter provides an overview of the BitBake tool and its role within the Yocto Project.
- Classes: This chapter describes the classes used in the Yocto Project.
- Images: This chapter describes the standard images that the Yocto Project supports.
- Features: This chapter describes mechanisms for creating distribution, machine, and image features during the build process using the OpenEmbedded build system.
- Variables Glossary: This chapter presents most variables used by the OpenEmbedded build system, which using BitBake. Entries describe the function of the variable and how to apply them.
- Variable Context: This chapter provides variable locality or context.
- FAQ: This chapter provides answers for commonly asked questions in the Yocto Project development environment.
- Contributing to the Yocto Project: This chapter provides guidance on how you can contribute back to the Yocto Project.

1.3. System Requirements

For general Yocto Project system requirements, see the "What You Need and How You Get It [<http://www.yoctoproject.org/docs/1.3/yocto-project-qs/yocto-project-qs.html#yp-resources>]" section in the Yocto Project Quick Start. The remainder of this section provides details on system requirements not covered in the Yocto Project Quick Start.

1.3.1. Supported Linux Distributions

Currently, the Yocto Project is supported on the following distributions:

- Ubuntu 10.04.4 LTS
- Ubuntu 11.10

- Ubuntu 12.04.1 LTS
- Ubuntu 12.04.1 LTS
- Ubuntu 12.10
- Fedora release 16 (Verne)
- Fedora release 17 (Beefy Miracle)
- Fedora release 18 (Spherical Cow)
- CentOS release 5.6 (Final)
- CentOS release 5.7 (Final)
- CentOS release 5.8 (Final)
- CentOS release 6.3 (Final)
- Debian GNU/Linux 6.0.6 (squeeze)
- openSUSE 11.4
- openSUSE 12.1
- openSUSE 12.2

Note

For additional information on distributions that support the Yocto Project, see the Distribution Support [https://wiki.yoctoproject.org/wiki/Distribution_Support] wiki page.

1.3.2. Required Packages for the Host Development System

The list of packages you need on the host development system can be large when covering all build scenarios using the Yocto Project. This section provides required packages by Linux distribution and further categorized by function.

1.3.2.1. Ubuntu

The following list shows the required packages by function given a supported Ubuntu Linux distribution:

- Essentials: Packages needed to build an image on a headless system:

```
$ sudo apt-get install awk wget git-core diffstat unzip texinfo build-essential chrpath
```

- Graphical Extras: Packages recommended if the host system has graphics support:

```
$ sudo apt-get install libsdl1.2-dev xterm
```

- Documentation: Packages needed if you are going to build out the Yocto Project documentation manuals:

```
$ sudo apt-get install make xsltproc docbook-utils fop
```

- ADT Installer Extras: Packages needed if you are going to be using the Application Development Toolkit (ADT) Installer [<http://www.yoctoproject.org/docs/1.3/adt-manual/adt-manual.html#using-the-adt-installer>]:

```
$ sudo apt-get install autoconf automake libtool libglib2.0-dev
```

1.3.2.2. Fedora Packages

The following list shows the required packages by function given a supported Fedora Linux distribution:

- Essentials: Packages needed to build an image for a headless system:

```
$ sudo yum install awk make wget tar bzip2 gzip python unzip perl patch diffutils diffstat  
cpp gcc gcc-c++ glibc-devel texinfo chrpath ccache
```

- Graphical Extras: Packages recommended if the host system has graphics support:

```
$ sudo yum install SDL-devel xterm
```

- Documentation: Packages needed if you are going to build out the Yocto Project documentation manuals:

```
$ sudo yum install make docbook-style-dsssl docbook-style-xsl \  
docbook-dtds docbook-utils fop libxslt
```

- ADT Installer Extras: Packages needed if you are going to be using the Application Development Toolkit (ADT) Installer [<http://www.yoctoproject.org/docs/1.3/adt-manual/adt-manual.html#using-the-adt-installer>]:

```
$ sudo yum install autoconf automake libtool glib2-devel
```

1.3.2.3. OpenSUSE Packages

The following list shows the required packages by function given a supported OpenSUSE Linux distribution:

- Essentials: Packages needed to build an image for a headless system:

```
$ sudo zypper install python gcc gcc-c++ git chrpath make wget diffstat texinfo python-curl
```

- Graphical Extras: Packages recommended if the host system has graphics support:

```
$ sudo zypper install libSDL-devel xterm
```

- Documentation: Packages needed if you are going to build out the Yocto Project documentation manuals:

```
$ sudo zypper install make fop xsltproc
```

- ADT Installer Extras: Packages needed if you are going to be using the Application Development Toolkit (ADT) Installer [<http://www.yoctoproject.org/docs/1.3/adt-manual/adt-manual.html#using-the-adt-installer>]:

```
$ sudo zypper install autoconf automake libtool glib2-devel
```

1.3.2.4. CentOS Packages

The following list shows the required packages by function given a supported CentOS Linux distribution:

- Essentials: Packages needed to build an image for a headless system:

```
$ sudo yum -y install gawk make wget tar bzip2 gzip python unzip perl patch diffutils diff  
cpp gcc gcc-c++ glibc-devel texinfo chrpath
```

- Graphical Extras: Packages recommended if the host system has graphics support:

```
$ sudo yum -y install SDL-devel xterm
```

- Documentation: Packages needed if you are going to build out the Yocto Project documentation manuals:

```
$ sudo yum -y install make docbook-style-dsssl docbook-style-xsl \  
docbook-dtds docbook-utils fop libxslt
```

- ADT Installer Extras: Packages needed if you are going to be using the Application Development Toolkit (ADT) Installer [<http://www.yoctoproject.org/docs/1.3/adt-manual/adt-manual.html#using-the-adt-installer>]:

```
$ sudo yum -y install autoconf automake libtool glib2-devel
```

Note

Depending on the CentOS version you are using, other requirements and dependencies might exist. For details, you should look at the CentOS sections on the Poky/GettingStarted/Dependencies [<https://wiki.yoctoproject.org/wiki/Poky/GettingStarted/Dependencies>] wiki page.

1.4. Obtaining the Yocto Project

The Yocto Project development team makes the Yocto Project available through a number of methods:

- Releases: Stable, tested releases are available through <http://downloads.yoctoproject.org/releases/yocto/>.
- Nightly Builds: These releases are available at <http://autobuilder.yoctoproject.org/nightly>. These builds include Yocto Project releases, meta-toolchain tarball installation scripts, and experimental builds.
- Yocto Project Website: You can find releases of the Yocto Project and supported BSPs at the Yocto Project website [<http://www.yoctoproject.org>]. Along with these downloads, you can find lots of other information at this site.

1.5. Development Checkouts

Development using the Yocto Project requires a local Source Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#source-directory>]. You can set up the source directory by downloading a Yocto Project release tarball and unpacking it, or by cloning a copy of the upstream Poky [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#poky>] Git repository. For

information on both these methods, see the "Getting Setup [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#getting-setup>]" section in the Yocto Project Development Manual.

Chapter 2. Using the Yocto Project

This chapter describes common usage for the Yocto Project. The information is introductory in nature as other manuals in the Yocto Project documentation set provide more details on how to use the Yocto Project.

2.1. Running a Build

You can find general information on how to build an image using the OpenEmbedded build system in the "Building an Image [<http://www.yoctoproject.org/docs/1.3/yocto-project-qs/yocto-project-qs.html#building-image>]" section of the Yocto Project Quick Start. This section provides a summary of the build process and provides information for less obvious aspects of the build process.

2.1.1. Build Overview

The first thing you need to do is set up the OpenEmbedded build environment by sourcing the environment setup script as follows:

```
$ source oe-init-build-env [build_dir]
```

The `build_dir` is optional and specifies the directory the OpenEmbedded build system uses for the build - the Build Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#build-directory>]. If you do not specify a Build Directory it defaults to build in your current working directory. A common practice is to use a different Build Directory for different targets. For example, `~/build/x86` for a `qemux86` target, and `~/build/arm` for a `qemuarm` target. See `oe-init-build-env` for more information on this script.

Once the build environment is set up, you can build a target using:

```
$ bitbake <target>
```

The target is the name of the recipe you want to build. Common targets are the images in `meta/recipes-core/images`, `/meta/recipes-sato/images`, etc. all found in the Source Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#source-directory>]. Or, the target can be the name of a recipe for a specific piece of software such as `busybox`. For more details about the images the OpenEmbedded build system supports, see the "Images" chapter.

Note

Building an image without GNU General Public License Version 3 (GPLv3) components is only supported for minimal and base images. See the "Images" chapter for more information.

2.1.2. Building an Image Using GPL Components

When building an image using GPL components, you need to maintain your original settings and not switch back and forth applying different versions of the GNU General Public License. If you rebuild using different versions of GPL, dependency errors might occur due to some components not being rebuilt.

2.2. Installing and Using the Result

Once an image has been built, it often needs to be installed. The images and kernels built by the OpenEmbedded build system are placed in the Build Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#build-directory>] in `tmp/deploy/images`. For information on how to run pre-built images such as `qemux86` and `qemuarm`, see the "Using Pre-Built Binaries and QEMU [<http://www.yoctoproject.org/docs/1.3/yocto-project-qs/yocto-project-qs.html#using-pre-built>]" section in the Yocto Project Quick Start. For information about how to install these images, see the documentation for your particular board/machine.

2.3. Debugging Build Failures

The exact method for debugging build failures depends on the nature of the problem and on the system's area from which the bug originates. Standard debugging practices such as comparison against the last known working version with examination of the changes and the re-application of steps to identify the one causing the problem are valid for the Yocto Project just as they are for any other system. Even though it is impossible to detail every possible potential failure, this section provides some general tips to aid in debugging.

2.3.1. Task Failures

The log file for shell tasks is available in `${WORKDIR}/temp/log.do_taskname.pid`. For example, the `compile` task for the QEMU minimal image for the x86 machine (`qemux86`) might be `tmp/work/qemux86-poky-linux/core-image-minimal-1.0-r0/temp/log.do_compile.20830`. To see what BitBake runs to generate that log, look at the corresponding `run.do_taskname.pid` file located in the same directory.

Presently, the output from Python tasks is sent directly to the console.

2.3.2. Running Specific Tasks

Any given package consists of a set of tasks. The standard BitBake behavior in most cases is: `fetch`, `unpack`, `patch`, `configure`, `compile`, `install`, `package`, `package_write`, and `build`. The default task is `build` and any tasks on which it depends build first. Some tasks exist, such as `devshell`, that are not part of the default build chain. If you wish to run a task that is not part of the default build chain, you can use the `-c` option in BitBake as follows:

```
$ bitbake matchbox-desktop -c devshell
```

If you wish to rerun a task, use the `-f` force option. For example, the following sequence forces recompilation after changing files in the working directory.

```
$ bitbake matchbox-desktop
      .
      .
      [make some changes to the source code in the working directory]
      .
      .
$ bitbake matchbox-desktop -c compile -f
$ bitbake matchbox-desktop
```

This sequence first builds `matchbox-desktop` and then recompiles it. The last command reruns all tasks (basically the packaging tasks) after the `compile`. BitBake recognizes that the `compile` task was rerun and therefore understands that the other tasks also need to be run again.

You can view a list of tasks in a given package by running the `listtasks` task as follows:

```
$ bitbake matchbox-desktop -c listtasks
```

The results are in the file `${WORKDIR}/temp/log.do_listtasks`.

2.3.3. Dependency Graphs

Sometimes it can be hard to see why BitBake wants to build some other packages before a given package you have specified. The `bitbake -g targetname` command creates the `depends.dot`, `package-depends.dot`, and `task-depends.dot` files in the current directory. These files show the package and task dependencies and are useful for debugging problems. You can use the `bitbake -g -u depexp targetname` command to display the results in a more human-readable form.

2.3.4. General BitBake Problems

You can see debug output from BitBake by using the `-D` option. The debug output gives more information about what BitBake is doing and the reason behind it. Each `-D` option you use increases the logging level. The most common usage is `-DDD`.

The output from `bitbake -DDD -v targetname` can reveal why BitBake chose a certain version of a package or why BitBake picked a certain provider. This command could also help you in a situation where you think BitBake did something unexpected.

2.3.5. Building with No Dependencies

If you really want to build a specific `.bb` file, you can use the command form `bitbake -b <somepath/somefile.bb>`. This command form does not check for dependencies so you should use it only when you know its dependencies already exist. You can also specify fragments of the filename. In this case, BitBake checks for a unique match.

2.3.6. Variables

The `-e` option dumps the resulting environment for either the configuration (no package specified) or for a specific package when specified; or `-b recipename` to show the environment from parsing a single recipe file only.

2.3.7. Recipe Logging Mechanisms

Best practices exist while writing recipes that both log build progress and act on build conditions such as warnings and errors. Both Python and Bash language bindings exist for the logging mechanism:

- Python: For Python functions, BitBake supports several loglevels: `bb.fatal`, `bb.error`, `bb.warn`, `bb.note`, `bb.plain`, and `bb.debug`.
- Bash: For Bash functions, the same set of loglevels exist and are accessed with a similar syntax: `bbfatal`, `bberror`, `bbwarn`, `bbnote`, `bbplain`, and `bbdebug`.

For guidance on how logging is handled in both Python and Bash recipes, see the `logging.bbclass` file in the `meta/classes` folder of the Source Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#source-directory>].

2.3.7.1. Logging With Python

When creating recipes using Python and inserting code that handles build logs keep in mind the goal is to have informative logs while keeping the console as "silent" as possible. Also, if you want status messages in the log use the "debug" loglevel.

Following is an example written in Python. The code handles logging for a function that determines the number of tasks needed to be run:

```
python do_listtasks() {
    bb.debug(2, "Starting to figure out the task list")
    if noteworthy_condition:
        bb.note("There are 47 tasks to run")
    bb.debug(2, "Got to point xyz")
    if warning_trigger:
        bb.warn("Detected warning_trigger, this might be a problem later.")
    if recoverable_error:
        bb.error("Hit recoverable_error, you really need to fix this!")
    if fatal_error:
        bb.fatal("fatal_error detected, unable to print the task list")
    bb.plain("The tasks present are abc")
    bb.debug(2, "Finished figuring out the tasklist")
}
```

2.3.7.2. Logging With Bash

When creating recipes using Bash and inserting code that handles build logs you have the same goals - informative with minimal console output. The syntax you use for recipes written in Bash is similar to that of recipes written in Python described in the previous section.

Following is an example written in Bash. The code logs the progress of the `do_my_function` function.

```
do_my_function() {
    bbdebug 2 "Running do_my_function"
    if [ exceptional_condition ]; then
        bbnote "Hit exceptional_condition"
    fi
    bbdebug 2 "Got to point xyz"
    if [ warning_trigger ]; then
        bbwarn "Detected warning_trigger, this might cause a problem later."
    fi
    if [ recoverable_error ]; then
        bberror "Hit recoverable_error, correcting"
    fi
    if [ fatal_error ]; then
        bbfatal "fatal_error detected"
    fi
    bbdebug 2 "Completed do_my_function"
}
```

2.3.8. Other Tips

Here are some other tips that you might find useful:

- When adding new packages, it is worth watching for undesirable items making their way into compiler command lines. For example, you do not want references to local system files like `/usr/lib/` or `/usr/include/`.
- If you want to remove the psplash boot splashscreen, add `psplash=false` to the kernel command line. Doing so prevents psplash from loading and thus allows you to see the console. It is also possible to switch out of the splashscreen by switching the virtual console (e.g. `Fn+Left` or `Fn+Right` on a Zaurus).

Chapter 3. Technical Details

This chapter provides technical details for various parts of the Yocto Project. Currently, topics include Yocto Project components and shared state (sstate) cache.

3.1. Yocto Project Components

The BitBake task executor together with various types of configuration files form the OpenEmbedded Core. This section overviews the BitBake task executor and the configuration files by describing what they are used for and how they interact.

BitBake handles the parsing and execution of the data files. The data itself is of various types:

- Recipes: Provides details about particular pieces of software
- Class Data: An abstraction of common build information (e.g. how to build a Linux kernel).
- Configuration Data: Defines machine-specific settings, policy decisions, etc. Configuration data acts as the glue to bind everything together.

For more information on data, see the "Yocto Project Terms [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#yocto-project-terms>]" section in the Yocto Project Development Manual.

BitBake knows how to combine multiple data sources together and refers to each data source as a layer. For information on layers, see the "Understanding and Creating Layers [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#understanding-and-creating-layers>]" section of the Yocto Project Development Manual.

Following are some brief details on these core components. For more detailed information on these components see the "Directory Structure" chapter.

3.1.1. BitBake

BitBake is the tool at the heart of the OpenEmbedded build system and is responsible for parsing the metadata, generating a list of tasks from it, and then executing those tasks. To see a list of the options BitBake supports, use the following help command:

```
$ bitbake --help
```

The most common usage for BitBake is `bitbake <packagename>`, where `packagename` is the name of the package you want to build (referred to as the "target" in this manual). The target often equates to the first part of a `.bb` filename. So, to run the `matchbox-desktop_1.2.3.bb` file, you might type the following:

```
$ bitbake matchbox-desktop
```

Several different versions of `matchbox-desktop` might exist. BitBake chooses the one selected by the distribution configuration. You can get more details about how BitBake chooses between different target versions and providers in the "Preferences and Providers" section.

BitBake also tries to execute any dependent tasks first. So for example, before building `matchbox-desktop`, BitBake would build a cross compiler and `eglibc` if they had not already been built.

Note

This release of the Yocto Project does not support the `glibc` GNU version of the Unix standard C library. By default, the OpenEmbedded build system builds with `eglibc`.

A useful BitBake option to consider is the `-k` or `--continue` option. This option instructs BitBake to try and continue processing the job as much as possible even after encountering an error. When an error occurs, the target that failed and those that depend on it cannot be remade. However, when you use this option other dependencies can still be processed.

3.1.2. Metadata (Recipes)

The `.bb` files are usually referred to as "recipes." In general, a recipe contains information about a single piece of software. The information includes the location from which to download the source patches (if any are needed), which special configuration options to apply, how to compile the source files, and how to package the compiled output.

The term "package" can also be used to describe recipes. However, since the same word is used for the packaged output from the OpenEmbedded build system (i.e. `.ipk` or `.deb` files), this document avoids using the term "package" when referring to recipes.

3.1.3. Classes

Class files (`.bbclass`) contain information that is useful to share between metadata files. An example is the Autotools class, which contains common settings for any application that Autotools uses. The "Classes" chapter provides details about common classes and how to use them.

3.1.4. Configuration

The configuration files (`.conf`) define various configuration variables that govern the OpenEmbedded build process. These files fall into several areas that define machine configuration options, distribution configuration options, compiler tuning options, general common configuration options and user configuration options (`local.conf`, which is found in the Build Directory [build-directory]).

3.2. Shared State Cache

By design, the OpenEmbedded build system builds everything from scratch unless BitBake can determine that parts don't need to be rebuilt. Fundamentally, building from scratch is attractive as it means all parts are built fresh and there is no possibility of stale data causing problems. When developers hit problems, they typically default back to building from scratch so they know the state of things from the start.

Building an image from scratch is both an advantage and a disadvantage to the process. As mentioned in the previous paragraph, building from scratch ensures that everything is current and starts from a known state. However, building from scratch also takes much longer as it generally means rebuilding things that don't necessarily need rebuilt.

The Yocto Project implements shared state code that supports incremental builds. The implementation of the shared state code answers the following questions that were fundamental roadblocks within the OpenEmbedded incremental build support system:

- What pieces of the system have changed and what pieces have not changed?
- How are changed pieces of software removed and replaced?
- How are pre-built components that don't need to be rebuilt from scratch used when they are available?

For the first question, the build system detects changes in the "inputs" to a given task by creating a checksum (or signature) of the task's inputs. If the checksum changes, the system assumes the inputs have changed and the task needs to be rerun. For the second question, the shared state (`sstate`) code tracks which tasks add which output to the build process. This means the output from a given task can be removed, upgraded or otherwise manipulated. The third question is partly addressed by the solution for the second question assuming the build system can fetch the `sstate` objects from remote locations and install them if they are deemed to be valid.

The rest of this section goes into detail about the overall incremental build architecture, the checksums (signatures), shared state, and some tips and tricks.

3.2.1. Overall Architecture

When determining what parts of the system need to be built, BitBake uses a per-task basis and does not use a per-recipe basis. You might wonder why using a per-task basis is preferred over a per-recipe basis. To help explain, consider having the IPK packaging backend enabled and then switching to DEB. In this case, `do_install` and `do_package` output are still valid. However, with a per-recipe approach,

the build would not include the .deb files. Consequently, you would have to invalidate the whole build and rerun it. Rerunning everything is not the best situation. Also in this case, the core must be "taught" much about specific tasks. This methodology does not scale well and does not allow users to easily add new tasks in layers or as external recipes without touching the packaged-staging core.

3.2.2. Checksums (Signatures)

The shared state code uses a checksum, which is a unique signature of a task's inputs, to determine if a task needs to be run again. Because it is a change in a task's inputs that triggers a rerun, the process needs to detect all the inputs to a given task. For shell tasks, this turns out to be fairly easy because the build process generates a "run" shell script for each task and it is possible to create a checksum that gives you a good idea of when the task's data changes.

To complicate the problem, there are things that should not be included in the checksum. First, there is the actual specific build path of a given task - the WORKDIR. It does not matter if the working directory changes because it should not affect the output for target packages. Also, the build process has the objective of making native/cross packages relocatable. The checksum therefore needs to exclude WORKDIR. The simplistic approach for excluding the working directory is to set WORKDIR to some fixed value and create the checksum for the "run" script.

Another problem results from the "run" scripts containing functions that might or might not get called. The incremental build solution contains code that figures out dependencies between shell functions. This code is used to prune the "run" scripts down to the minimum set, thereby alleviating this problem and making the "run" scripts much more readable as a bonus.

So far we have solutions for shell scripts. What about python tasks? The same approach applies even though these tasks are more difficult. The process needs to figure out what variables a python function accesses and what functions it calls. Again, the incremental build solution contains code that first figures out the variable and function dependencies, and then creates a checksum for the data used as the input to the task.

Like the WORKDIR case, situations exist where dependencies should be ignored. For these cases, you can instruct the build process to ignore a dependency by using a line like the following:

```
PACKAGE_ARCHS[vardepsexclude] = "MACHINE"
```

This example ensures that the PACKAGE_ARCHS variable does not depend on the value of MACHINE, even if it does reference it.

Equally, there are cases where we need to add dependencies BitBake is not able to find. You can accomplish this by using a line like the following:

```
PACKAGE_ARCHS[vardeps] = "MACHINE"
```

This example explicitly adds the MACHINE variable as a dependency for PACKAGE_ARCHS.

Consider a case with inline python, for example, where BitBake is not able to figure out dependencies. When running in debug mode (i.e. using -DDD), BitBake produces output when it discovers something for which it cannot figure out dependencies. The Yocto Project team has currently not managed to cover those dependencies in detail and is aware of the need to fix this situation.

Thus far, this section has limited discussion to the direct inputs into a task. Information based on direct inputs is referred to as the "basehash" in the code. However, there is still the question of a task's indirect inputs - the things that were already built and present in the Build Directory. The checksum (or signature) for a particular task needs to add the hashes of all the tasks on which the particular task depends. Choosing which dependencies to add is a policy decision. However, the effect is to generate a master checksum that combines the basehash and the hashes of the task's dependencies.

At the code level, there are a variety of ways both the basehash and the dependent task hashes can be influenced. Within the BitBake configuration file, we can give BitBake some extra information to help it construct the basehash. The following statements effectively result in a list of global variable dependency excludes - variables never included in any checksum:

```
BB_HASHBASE_WHITELIST ?= "TMPDIR FILE_PATH PWD BB_TASKHASH BBPATH"
BB_HASHBASE_WHITELIST += "DL_DIR SSTATE_DIR THISDIR FILESEXTRAPATHS"
BB_HASHBASE_WHITELIST += "FILE_DIRNAME HOME LOGNAME SHELL TERM USER"
BB_HASHBASE_WHITELIST += "FILESPATH USERNAME STAGING_DIR_HOST STAGING_DIR_TARGET"
```

The previous example actually excludes WORKDIR since it is actually constructed as a path within TMPDIR, which is on the whitelist.

The rules for deciding which hashes of dependent tasks to include through dependency chains are more complex and are generally accomplished with a python function. The code in meta/lib/oe/sstatesig.py shows two examples of this and also illustrates how you can insert your own policy into the system if so desired. This file defines the two basic signature generators OE-Core uses: "OEBasic" and "OEBasicHash". By default, there is a dummy "noop" signature handler enabled in BitBake. This means that behavior is unchanged from previous versions. OE-Core uses the "OEBasic" signature handler by default through this setting in the bitbake.conf file:

```
BB_SIGNATURE_HANDLER ?= "OEBasic"
```

The "OEBasicHash" BB_SIGNATURE_HANDLER is the same as the "OEBasic" version but adds the task hash to the stamp files. This results in any metadata change that changes the task hash, automatically causing the task to be run again. This removes the need to bump PR values and changes to metadata automatically ripple across the build. Currently, this behavior is not the default behavior for OE-Core but is the default in poky.

It is also worth noting that the end result of these signature generators is to make some dependency and hash information available to the build. This information includes:

```
BB_BASEHASH_task-<taskname> - the base hashes for each task in the recipe
BB_BASEHASH_<filename:taskname> - the base hashes for each dependent task
BBHASHDEPS_<filename:taskname> - The task dependencies for each task
BB_TASKHASH - the hash of the currently running task
```

3.2.3. Shared State

Checksums and dependencies, as discussed in the previous section, solve half the problem. The other part of the problem is being able to use checksum information during the build and being able to reuse or rebuild specific components.

The shared state class (sstate.bbclass) is a relatively generic implementation of how to "capture" a snapshot of a given task. The idea is that the build process does not care about the source of a task's output. Output could be freshly built or it could be downloaded and unpacked from somewhere - the build process doesn't need to worry about its source.

There are two types of output, one is just about creating a directory in WORKDIR. A good example is the output of either do_install or do_package. The other type of output occurs when a set of data is merged into a shared directory tree such as the sysroot.

The Yocto Project team has tried to keep the details of the implementation hidden in sstate.bbclass. From a user's perspective, adding shared state wrapping to a task is as simple as this do_deploy example taken from do_deploy.bbclass:

```
DEPLOYDIR = "${WORKDIR}/deploy-${PN}"
SSTATETASKS += "do_deploy"
do_deploy[sstate-name] = "deploy"
do_deploy[sstate-inputdirs] = "${DEPLOYDIR}"
do_deploy[sstate-outputdirs] = "${DEPLOY_DIR_IMAGE}"

python do_deploy_setscene () {
    sstate_setscene(d)
}
addtask do_deploy_setscene
```

In the example, we add some extra flags to the task, a name field ("deploy"), an input directory where the task sends data, and the output directory where the data from the task should eventually be copied. We also add a `_setscene` variant of the task and add the task name to the `SSTATETASKS` list.

If you have a directory whose contents you need to preserve, you can do this with a line like the following:

```
do_package[sstate-plaindirs] = "${PKGD} ${PKGDEST}"
```

This method, as well as the following example, also works for multiple directories.

```
do_package[sstate-inputdirs] = "${PKGDESTWORK} ${SHLIBSWORKDIR}"
do_package[sstate-outputdirs] = "${PKGDATA_DIR} ${SHLIBSDIR}"
do_package[sstate-lockfile] = "${PACKAGELOCK}"
```

These methods also include the ability to take a lockfile when manipulating shared state directory structures since some cases are sensitive to file additions or removals.

Behind the scenes, the shared state code works by looking in `SSTATE_DIR` and `SSTATE_MIRRORS` for shared state files. Here is an example:

```
SSTATE_MIRRORS ?= "\
file://.* http://someserver.tld/share/sstate/PATH \n \
file://.* file:///some/local/dir/sstate/PATH"
```

Note

The shared state directory (`SSTATE_DIR`) is organized into two-character subdirectories, where the subdirectory names are based on the first two characters of the hash. If the shared state directory structure for a mirror has the same structure as `SSTATE_DIR`, you must specify "PATH" as part of the URI to enable the build system to map to the appropriate subdirectory.

The shared state package validity can be detected just by looking at the filename since the filename contains the task checksum (or signature) as described earlier in this section. If a valid shared state package is found, the build process downloads it and uses it to accelerate the task.

The build processes uses the `*_setscene` tasks for the task acceleration phase. BitBake goes through this phase before the main execution code and tries to accelerate any tasks for which it can find shared state packages. If a shared state package for a task is available, the shared state package is used. This means the task and any tasks on which it is dependent are not executed.

As a real world example, the aim is when building an IPK-based image, only the `do_package_write_ipk` tasks would have their shared state packages fetched and extracted. Since the `sysroot` is not used, it would never get extracted. This is another reason why a task-based approach is preferred over a recipe-based approach, which would have to install the output from every task.

3.2.4. Tips and Tricks

The code in the build system that supports incremental builds is not simple code. This section presents some tips and tricks that help you work around issues related to shared state code.

3.2.4.1. Debugging

When things go wrong, debugging needs to be straightforward. Because of this, the Yocto Project team included strong debugging tools:

- Whenever a shared state package is written out, so is a corresponding `.siginfo` file. This practice results in a pickled python database of all the metadata that went into creating the hash for a given shared state package.

- If BitBake is run with the `--dump-signatures` (or `-S`) option, BitBake dumps out `.siginfo` files in the stamp directory for every task it would have executed instead of building the specified target package.
- There is a `bitbake-diffsigs` command that can process these `.siginfo` files. If one file is specified, it will dump out the dependency information in the file. If two files are specified, it will compare the two files and dump out the differences between the two. This allows the question of "What changed between X and Y?" to be answered easily.

3.2.4.2. Invalidating Shared State

The shared state code uses checksums and shared state cache to avoid unnecessarily rebuilding tasks. As with all schemes, this one has some drawbacks. It is possible that you could make implicit changes that are not factored into the checksum calculation, but do affect a task's output. A good example is perhaps when a tool changes its output. Let's say that the output of `rpmdeps` needed to change. The result of the change should be that all the "package", "package_write_rpm", and "package_deploy-rpm" shared state cache items would become invalid. But, because this is a change that is external to the code and therefore implicit, the associated shared state cache items do not become invalidated. In this case, the build process would use the cached items rather than running the task again. Obviously, these types of implicit changes can cause problems.

To avoid these problems during the build, you need to understand the effects of any change you make. Note that any changes you make directly to a function automatically are factored into the checksum calculation and thus, will invalidate the associated area of sstate cache. You need to be aware of any implicit changes that are not obvious changes to the code and could affect the output of a given task. Once you are aware of such a change, you can take steps to invalidate the cache and force the task to run. The step to take is as simple as changing a function's comments in the source code. For example, to invalidate package shared state files, change the comment statements of `do_package` or the comments of one of the functions it calls. The change is purely cosmetic, but it causes the checksum to be recalculated and forces the task to be run again.

Note

For an example of a commit that makes a cosmetic change to invalidate a shared state, see this commit [<http://git.yoctoproject.org/cgi/poky/commit/meta/classes/package.bbclass?id=737f8bbb4f27b4837047cb9b4fbfe01dfde36d54>].

3.3. x32

x32 is a new processor-specific Application Binary Interface (psABI) for x86_64. An ABI defines the calling conventions between functions in a processing environment. The interface determines what registers are used and what the sizes are for various C data types.

Some processing environments prefer using 32-bit applications even when running on Intel 64-bit platforms. Consider the i386 psABI, which is a very old 32-bit ABI for Intel 64-bit platforms. The i386 psABI does not provide efficient use and access of the Intel 64-bit processor resources, leaving the system underutilized. Now consider the x86_64 psABI. This ABI is newer and uses 64-bits for data sizes and program pointers. The extra bits increase the footprint size of the programs, libraries, and also increases the memory and file system size requirements. Executing under the x32 psABI enables user programs to utilize CPU and system resources more efficiently while keeping the memory footprint of the applications low. Extra bits are used for registers but not for addressing mechanisms.

3.3.1. Support

While the x32 psABI specifications are not fully finalized, this Yocto Project release supports current development specifications of x32 psABI. As of this release of the Yocto Project, x32 psABI support exists as follows:

- You can create packages and images in x32 psABI format on x86_64 architecture targets.
- You can use the x32 psABI support through the meta-x32 layer on top of the OE-core/Yocto layer.
- The toolchain from the experimental/meta-x32 layer is used for building x32 psABI program binaries.
- You can successfully build many recipes with the x32 toolchain.

- You can create and boot `core-image-minimal` and `core-image-sato` images.

3.3.2. Future Development and Limitations

As of this Yocto Project release, the x32 psABI kernel and library interfaces specifications are not finalized.

Future Plans for the x32 psABI in the Yocto Project include the following:

- Enhance and fix the few remaining recipes so they work with and support x32 toolchains.
- Enhance RPM Package Manager (RPM) support for x32 binaries.
- Support larger images.
- Integrate x32 recipes, toolchain, and kernel changes from `experimental/meta-x32` into `OE-core`.

3.3.3. Using x32 Right Now

Despite the fact the x32 psABI support is in development state for this release of the Yocto Project, you can follow these steps to use the x32 spABI:

- Add the `experimental/meta-x32` layer to your local Build Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#build-directory>]. You can find the `experimental/meta-x32` source repository at <http://git.yoctoproject.org>.
- Edit your `conf/bblayers.conf` file so that it includes the `meta-x32`. Here is an example:

```
BBLAYERS ?= " \
    /home/nitin/prj/poky.git/meta \
    /home/nitin/prj/poky.git/meta-yocto \
    /home/nitin/prj/poky.git/meta-yocto-bsp \
    /home/nitin/prj/meta-x32.git \
"
```

- Enable the x32 psABI tuning file for `x86_64` machines by editing the `conf/local.conf` like this:

```
MACHINE = "qemux86-64"
DEFAULTTUNE = "x86-64-x32"
baselib = "${@d.getVar('BASE_LIB_tune-' + (d.getVar('DEFAULTTUNE', True) \
    or 'INVALID'), True) or 'lib'}"
#MACHINE = "atom-pc"
#DEFAULTTUNE = "core2-64-x32"
```

- As usual, use BitBake to build an image that supports the x32 psABI. Here is an example:

```
$ bitake core-image-sato
```

- As usual, run your image using QEMU:

```
$ runqemu qemux86-64 core-image-sato
```

3.4. Licenses

This section describes the mechanism by which the OpenEmbedded build system tracks changes to licensing text. The section also describes how to enable commercially licensed recipes, which by default are disabled.

For information that can help you maintain compliance with various open source licensing during the lifecycle of the product, see the "Maintaining Open Source License Compliance During Your Project's Lifecycle [http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#maintaining-open-source-license-compliance-during-your-products-lifecycle]" section in the Yocto Project Development Manual.

3.4.1. Tracking License Changes

The license of an upstream project might change in the future. In order to prevent these changes going unnoticed, the `LIC_FILES_CHKSUM` variable tracks changes to the license text. The checksums are validated at the end of the configure step, and if the checksums do not match, the build will fail.

3.4.1.1. Specifying the `LIC_FILES_CHKSUM` Variable

The `LIC_FILES_CHKSUM` variable contains checksums of the license text in the source code for the recipe. Following is an example of how to specify `LIC_FILES_CHKSUM`:

```
LIC_FILES_CHKSUM = "file://COPYING;md5=xxxx \  
                    file://licfile1.txt;beginline=5;endline=29;md5=yyyy \  
                    file://licfile2.txt;endline=50;md5=zzzz \  
                    ..."
```

The build system uses the `S` variable as the default directory used when searching files listed in `LIC_FILES_CHKSUM`. The previous example employs the default directory.

You can also use relative paths as shown in the following example:

```
LIC_FILES_CHKSUM = "file://src/ls.c;beginline=5;endline=16;\  
                    md5=bb14ed3c4cda583abc85401304b5cd4e"  
LIC_FILES_CHKSUM = "file://../license.html;md5=5c94767cedb5d6987c902ac850ded2c6"
```

In this example, the first line locates a file in `${S}/src/ls.c`. The second line refers to a file in `WORKDIR`, which is the parent of `S`.

Note that this variable is mandatory for all recipes, unless the `LICENSE` variable is set to "CLOSED".

3.4.1.2. Explanation of Syntax

As mentioned in the previous section, the `LIC_FILES_CHKSUM` variable lists all the important files that contain the license text for the source code. It is possible to specify a checksum for an entire file, or a specific section of a file (specified by beginning and ending line numbers with the "beginline" and "endline" parameters, respectively). The latter is useful for source files with a license notice header, README documents, and so forth. If you do not use the "beginline" parameter, then it is assumed that the text begins on the first line of the file. Similarly, if you do not use the "endline" parameter, it is assumed that the license text ends with the last line of the file.

The "md5" parameter stores the md5 checksum of the license text. If the license text changes in any way as compared to this parameter then a mismatch occurs. This mismatch triggers a build failure and notifies the developer. Notification allows the developer to review and address the license text changes. Also note that if a mismatch occurs during the build, the correct md5 checksum is placed in the build log and can be easily copied to the recipe.

There is no limit to how many files you can specify using the `LIC_FILES_CHKSUM` variable. Generally, however, every project requires a few specifications for license tracking. Many projects have a "COPYING" file that stores the license information for all the source code files. This practice allows you to just track the "COPYING" file as long as it is kept up to date.

Tip

If you specify an empty or invalid "md5" parameter, BitBake returns an md5 mis-match error and displays the correct "md5" parameter value during the build. The correct parameter is also captured in the build log.

Tip

If the whole file contains only license text, you do not need to use the "beginline" and "endline" parameters.

3.4.2. Enabling Commercially Licensed Recipes

By default, the OpenEmbedded build system disables components that have commercial or other special licensing requirements. Such requirements are defined on a recipe-by-recipe basis through the LICENSE_FLAGS variable definition in the affected recipe. For instance, the \$HOME/poky/meta/recipes-multimedia/gstreamer/gst-plugins-ugly recipe contains the following statement:

```
LICENSE_FLAGS = "commercial"
```

Here is a slightly more complicated example that contains both an explicit recipe name and version (after variable expansion):

```
LICENSE_FLAGS = "license_${PN}_${PV}"
```

In order for a component restricted by a LICENSE_FLAGS definition to be enabled and included in an image, it needs to have a matching entry in the global LICENSE_FLAGS_WHITELIST variable, which is a variable typically defined in your local.conf file. For example, to enable the \$HOME/poky/meta/recipes-multimedia/gstreamer/gst-plugins-ugly package, you could add either the string "commercial_gst-plugins-ugly" or the more general string "commercial" to LICENSE_FLAGS_WHITELIST. See the "License Flag Matching" section for a full explanation of how LICENSE_FLAGS matching works. Here is the example:

```
LICENSE_FLAGS_WHITELIST = "commercial_gst-plugins-ugly"
```

Likewise, to additionally enable the package built from the recipe containing LICENSE_FLAGS = "license_\${PN}_\${PV}", and assuming that the actual recipe name was emgd_1.10.bb, the following string would enable that package as well as the original gst-plugins-ugly package:

```
LICENSE_FLAGS_WHITELIST = "commercial_gst-plugins-ugly license_emgd_1.10"
```

As a convenience, you do not need to specify the complete license string in the whitelist for every package. you can use an abbreviated form, which consists of just the first portion or portions of the license string before the initial underscore character or characters. A partial string will match any license that contains the given string as the first portion of its license. For example, the following whitelist string will also match both of the packages previously mentioned as well as any other packages that have licenses starting with "commercial" or "license".

```
LICENSE_FLAGS_WHITELIST = "commercial license"
```

3.4.2.1. License Flag Matching

The definition of 'matching' in reference to a recipe's LICENSE_FLAGS setting is simple. However, some things exist that you should know about in order to correctly and effectively use it.

Before a flag defined by a particular recipe is tested against the contents of the LICENSE_FLAGS_WHITELIST variable, the string_\${PN} (with PN expanded of course) is appended to the flag, thus automatically making each LICENSE_FLAGS value recipe-specific. That string is then matched against the whitelist. So if you specify LICENSE_FLAGS = "commercial" in recipe "foo" for example, the string "commercial_foo" would normally be what is specified in the whitelist in order for it to match.

You can broaden the match by putting any "-"separated beginning subset of a LICENSE_FLAGS flag in the whitelist, which will also match. For example, simply specifying "commercial" in the whitelist would match any expanded LICENSE_FLAGS definition starting with "commercial" such as "commercial_foo" and "commercial_bar", which are the strings that would be automatically generated for hypothetical "foo" and "bar" recipes assuming those recipes had simply specified the following:

```
LICENSE_FLAGS = "commercial"
```

Broadening the match allows for a range of specificity for the items in the whitelist, from more general to perfectly specific. So you have the choice of exhaustively enumerating each license flag in the whitelist to allow only those specific recipes into the image, or of using a more general string to pick up anything matching just the first component or components of the specified string.

This scheme works even if the flag already has `_${PN}` appended - the extra `_${PN}` is redundant, but does not affect the outcome. For example, a license flag of "commercial_1.2_foo" would turn into "commercial_1.2_foo_foo" and would match both the general "commercial" and the specific "commercial_1.2_foo", as expected. The flag would also match "commercial_1.2_foo_foo" and "commercial_1.2", which does not make much sense regarding use in the whitelist.

For a versioned string, you could instead specify "commercial_foo_1.2", which would turn into "commercial_foo_1.2_foo". And, as expected, this flag allows you to pick up this package along with anything else "commercial" when you specify "commercial" in the whitelist. Or, the flag allows you to pick up this package along with anything "commercial_foo" regardless of version when you use "commercial_foo" in the whitelist. Finally, you can be completely specific about the package and version and specify "commercial_foo_1.2" package and version.

3.4.2.2. Other Variables Related to Commercial Licenses

Other helpful variables related to commercial license handling exist and are defined in the `$HOME/poky/meta/conf/distro/include/default-distrovars.inc` file:

```
COMMERCIAL_AUDIO_PLUGINS ?= ""
COMMERCIAL_VIDEO_PLUGINS ?= ""
COMMERCIAL_QT = ""
```

If you want to enable these components, you can do so by making sure you have the following statements in your `local.conf` configuration file:

```
COMMERCIAL_AUDIO_PLUGINS = "gst-plugins-ugly-mad \
    gst-plugins-ugly-mpegaudioparse"
COMMERCIAL_VIDEO_PLUGINS = "gst-plugins-ugly-mpeg2dec \
    gst-plugins-ugly-mpegstream gst-plugins-bad-mpegvideoparse"
COMMERCIAL_QT ?= "qmp"
LICENSE_FLAGS_WHITELIST = "commercial_gst-plugins-ugly commercial_gst-plugins-bad commercial_qt"
```

Of course, you could also create a matching whitelist for those components using the more general "commercial" in the whitelist, but that would also enable all the other packages with LICENSE_FLAGS containing "commercial", which you may or may not want:

```
LICENSE_FLAGS_WHITELIST = "commercial"
```

Specifying audio and video plug-ins as part of the `COMMERCIAL_AUDIO_PLUGINS` and `COMMERCIAL_VIDEO_PLUGINS` statements or commercial qt components as part of the `COMMERCIAL_QT` statement (along with the enabling `LICENSE_FLAGS_WHITELIST`) includes the plug-ins or components into built images, thus adding support for media formats or components.

Chapter 4. Migrating to a Newer Yocto Project Release

This chapter provides information you can use to migrate work to a newer Yocto Project release. You can find the same information in the release notes for a given release.

4.1. Moving to the Yocto Project 1.3 Release

This section provides migration information for moving to the Yocto Project 1.3 Release.

4.1.1. Local Configuration

Differences include changes for `SSTATE_MIRRORS` and `bblayers.conf`.

4.1.1.1. SSTATE_MIRRORS

The shared state cache (`sstate-cache`) as pointed to by `SSTATE_DIR` by default now has two-character subdirectories to prevent there being an issue with too many files in the same directory. Also, native `sstate-cache` packages will go into a subdirectory named using the distro ID string. If you copy the newly structured `sstate-cache` to a mirror location (either local or remote) and then point to it in `SSTATE_MIRRORS`, you need to append "PATH" to the end of the mirror URL so that the path used by BitBake before the mirror substitution is appended to the path used to access the mirror. Here is an example:

```
SSTATE_MIRRORS = "file://.* http://someserver.tld/share/sstate/PATH"
```

4.1.1.2. bblayers.conf

The `meta-yocto` layer has been split into two parts: `meta-yocto` and `meta-yocto-bsp`, corresponding to the Poky reference distro configuration and the reference hardware Board Support Packages (BSPs), respectively. When running BitBake or Hob for the first time after upgrading, your `conf/bblayers.conf` file will be updated to handle this change and you will be asked to re-run/restart for the changes to take effect.

4.1.2. Recipes

Differences include changes for the following:

- Python function whitespace
- `proto=` in `SRC_URI`
- `nativesdk`
- Task recipes
- `IMAGE_FEATURES`
- Removed recipes

4.1.2.1. Python Function Whitespace

All Python functions must now use four spaces for indentation. Previously, an inconsistent mix of spaces and tabs existed, which made extending these functions using `_append` or `_prepend` complicated given that Python treats whitespace as syntactically significant. If you are defining or extending any Python functions (e.g. `populate_packages`, `do_unpack`, `do_patch` and so forth) in custom recipes or classes, you need to ensure you are using consistent four-space indentation.

4.1.2.2. proto= in SRC_URI

Any use of proto= in SRC_URI needs to be changed to protocol=. In particular, this applies to the following URIs:

- svn://
- bazaar://
- hg://
- osc://

Other URIs were already using protocol=. This change improves consistency.

4.1.2.3. nativesdk

The suffix nativesdk is now implemented as a prefix, which simplifies a lot of the packaging code for nativesdk recipes. All custom nativesdk recipes and any references need to be updated to use nativesdk-* instead of *-nativesdk.

4.1.2.4. Task Recipes

"Task" recipes are now known as "Package groups" and have been renamed from task-*.bb to packagegroup-*.bb. Existing references to the previous task-* names should work in most cases as there is an automatic upgrade path for most packages. However, you should update references in your own recipes and configurations as they could be removed in future releases. You should also rename any custom task-* recipes to packagegroup-*, and change them to inherit packagegroup instead of task, as well as taking the opportunity to remove anything now handled by packagegroup.bbclass, such as providing -dev and -dbg packages, setting LIC_FILES_CHKSUM, and so forth. See the "Package Groups - packagegroup.bbclass" section for further details.

4.1.2.5. IMAGE_FEATURES

Image recipes that previously included "apps-console-core" in IMAGE_FEATURES should now include "splash" instead to enable the boot-up splash screen. Retaining "apps-console-core" will still include the splash screen generates a warning. The "apps-x11-core" and "apps-x11-games" IMAGE_FEATURES features have been removed.

4.1.2.6. Removed Recipes

The following recipes have been removed. For most of them, it is unlikely that you would have any references to them in your own metadata. However, you should check your metadata against this list to be sure:

- libx11-trim: Replaced by libx11, which has a negligible size difference with modern Xorg.
- xserver-xorg-lite: Use xserver-xorg, which has a negligible size difference when DRI and GLX modules are not installed.
- xserver-kdrive: Effectively unmaintained for many years.
- mesa-xlib: No longer serves any purpose.
- galago: Replaced by telepathy.
- gail: Functionality was integrated into GTK+ 2.13.
- eggdbus: No longer needed.
- gcc-*-intermediate: The build has been restructured to avoid the need for this step.
- libgsmd: Unmaintained for many years. Functionality now provided by ofono instead.
- contacts, dates, tasks, eds-tools: Largely unmaintained PIM application suite. It has been moved to meta-gnome in meta-openembedded.

In addition to the previously listed changes, the meta-demoapps directory has also been removed because the recipes in it were not being maintained and many had become obsolete or broken. Additionally, these recipes were not parsed in the default configuration. Many of these recipes are already provided in an updated and maintained form within OpenEmbedded community layers such as meta-oe and meta-gnome. For the remainder, you can now find them in the meta-extras repository, which is in the Yocto Project source repositories.

Chapter 5. Source Directory Structure

The Source Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#source-directory>] consists of several components. Understanding them and knowing where they are located is key to using the Yocto Project well. This chapter describes the Source Directory and gives information about the various files and directories.

For information on how to establish a local Source Directory on your development system, see the "Getting Set Up [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#getting-setup>]" section in the Yocto Project Development Manual.

5.1. Top level core components

5.1.1. **bitbake/**

The Source Directory [source-directory] includes a copy of BitBake for ease of use. The copy usually matches the current stable BitBake release from the BitBake project. BitBake, a metadata interpreter, reads the Yocto Project metadata and runs the tasks defined by that data. Failures are usually from the metadata and not from BitBake itself. Consequently, most users do not need to worry about BitBake.

When you run the `bitbake` command, the wrapper script in `scripts/` is executed to run the main BitBake executable, which resides in the `bitbake/bin/` directory. Sourcing the `oe-init-build-env` script places the `scripts` and `bitbake/bin` directories (in that order) into the shell's `PATH` environment variable.

For more information on BitBake, see the BitBake documentation included in the `bitbake/doc/manual` directory of the Source Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#source-directory>].

5.1.2. **build/**

This directory contains user configuration files and the output generated by the OpenEmbedded build system in its standard configuration where the source tree is combined with the output. The Build Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#build-directory>] is created initially when you source the OpenEmbedded build environment setup script `oe-init-build-env`.

It is also possible to place output and configuration files in a directory separate from the Source Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#source-directory>] by providing a directory name when you source the setup script. For information on separating output from your local Source Directory files, see `oe-init-build-env`.

5.1.3. **documentation**

This directory holds the source for the Yocto Project documentation as well as templates and tools that allow you to generate PDF and HTML versions of the manuals. Each manual is contained in a sub-folder. For example, the files for this manual reside in `poky-ref-manual`.

5.1.4. **meta/**

This directory contains the OpenEmbedded Core metadata. The directory holds recipes, common classes, and machine configuration for emulated targets (`qemux86`, `qemuarm`, and so on.)

5.1.5. **meta-yocto/**

This directory contains the configuration for the Poky reference distribution.

5.1.6. meta-yocto-bsp/

This directory contains the Yocto Project reference hardware BSPs.

5.1.7. meta-hob/

This directory contains template recipes used by the Hob [<http://www.yoctoproject.org/projects/hob>] build UI.

5.1.8. meta-skeleton/

This directory contains template recipes for BSP and kernel development.

5.1.9. scripts/

This directory contains various integration scripts that implement extra functionality in the Yocto Project environment (e.g. QEMU scripts). The `oe-init-build-env` script appends this directory to the shell's `PATH` environment variable.

The `scripts` directory has useful scripts that assist contributing back to the Yocto Project, such as `create_pull_request` and `send_pull_request`.

5.1.10. oe-init-build-env

This script sets up the OpenEmbedded build environment. Running this script with the `source` command in a shell makes changes to `PATH` and sets other core BitBake variables based on the current working directory. You need to run this script before running BitBake commands. The script uses other scripts within the `scripts` directory to do the bulk of the work.

By default, running this script without a Build Directory argument creates the build directory. If you provide a Build Directory argument when you source the script, you direct OpenEmbedded build system to create a Build Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#build-directory>] of your choice. For example, the following command creates a Build Directory named `mybuilds` that is outside of the Source Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#source-directory>]:

```
$ source oe-init-build-env ~/mybuilds
```

5.1.11. LICENSE, README, and README.hardware

These files are standard top-level files.

5.2. The Build Directory -**build**/

5.2.1. build/pseudodone

This tag file indicates that the initial pseudo binary was created. The file is built the first time BitBake is invoked.

5.2.2. build/conf/local.conf

This file contains all the local user configuration for your build environment. If there is no `local.conf` present, it is created from `local.conf.sample`. The `local.conf` file contains documentation on the various configuration options. Any variable set here overrides any variable set elsewhere within the environment unless that variable is hard-coded within a file (e.g. by using `'='` instead of `'?='`). Some variables are hard-coded for various reasons but these variables are relatively rare.

Edit this file to set the `MACHINE` for which you want to build, which package types you wish to use (`PACKAGE_CLASSES`), where you want to download files (`DL_DIR`), and how you want your host machine to use resources (`BB_NUMBER_THREADS` and `PARALLEL_MAKE`).

5.2.3. **build/conf/bblayers.conf**

This file defines layers, which is a directory tree, traversed (or walked) by BitBake. If `bblayers.conf` is not present, it is created from `bblayers.conf.sample` when you source the environment setup script.

5.2.4. **build/conf/sanity_info**

This file is created during the build to indicate the state of the sanity checks.

5.2.5. **build/downloads/**

This directory is used for the upstream source tarballs. The directory can be reused by multiple builds or moved to another location. You can control the location of this directory through the `DL_DIR` variable.

5.2.6. **build/sstate-cache/**

This directory is used for the shared state cache. The directory can be reused by multiple builds or moved to another location. You can control the location of this directory through the `SSTATE_DIR` variable.

5.2.7. **build/tmp/**

This directory receives all the OpenEmbedded build system's output. BitBake creates this directory if it does not exist. As a last resort, to clean up a build and start it from scratch (other than the downloads), you can remove everything in the `tmp` directory or get rid of the directory completely. If you do, you should also completely remove the `build/sstate-cache` directory as well.

5.2.8. **build/tmp/buildstats/**

This directory stores the build statistics.

5.2.9. **build/tmp/cache/**

When BitBake parses the metadata, it creates a cache file of the result that can be used when subsequently running commands. These results are stored here on a per-machine basis.

5.2.10. **build/tmp/deploy/**

This directory contains any 'end result' output from the OpenEmbedded build process.

5.2.11. **build/tmp/deploy/deb/**

This directory receives any `.deb` packages produced by the build process. The packages are sorted into feeds for different architecture types.

5.2.12. **build/tmp/deploy/rpm/**

This directory receives any `.rpm` packages produced by the build process. The packages are sorted into feeds for different architecture types.

5.2.13. **build/tmp/deploy/licenses/**

This directory receives package licensing information. For example, the directory contains sub-directories for `bash`, `busybox`, and `eglibc` (among others) that in turn contain appropriate `COPYING` license files with other licensing information.

5.2.14. **build/tmp/deploy/images/**

This directory receives complete filesystem images. If you want to flash the resulting image from a build onto a device, look here for the image.

Be careful when deleting files in this directory. You can safely delete old images from this directory (e.g. `core-image-*`, `hob-image-*`, etc.). However, the kernel (`*zImage*`, `*uImage*`, etc.), bootloader and other supplementary files might be deployed here prior to building an image. Because these files, however, are not directly produced from the image, if you delete them they will not be automatically re-created when you build the image again.

If you do accidentally delete files here, you will need to force them to be re-created. In order to do that, you will need to know the target that produced them. For example, these commands rebuild and re-create the kernel files:

```
$ bitbake -c clean virtual/kernel
$ bitbake virtual/kernel
```

5.2.15. **build/tmp/deploy/ipk/**

This directory receives `.ipk` packages produced by the build process.

5.2.16. **build/tmp/sysroots/**

This directory contains shared header files and libraries as well as other shared data. Packages that need to share output with other packages do so within this directory. The directory is subdivided by architecture so multiple builds can run within the one Build Directory.

5.2.17. **build/tmp/stamps/**

This directory holds information that that BitBake uses for accounting purposes to track what tasks have run and when they have run. The directory is sub-divided by architecture. The files in the directory are empty of data. However, BitBake uses the filenames and timestamps for tracking purposes.

5.2.18. **build/tmp/log/**

This directory contains general logs that are not otherwise placed using the package's `WORKDIR`. Examples of logs are the output from the `check_pkg` or `distro_check` tasks. Running a build does not necessarily mean this directory is created.

5.2.19. **build/tmp/pkgdata/**

This directory contains intermediate packaging data that is used later in the packaging process. For more information, see the "Packaging - `package*.bbclass`" section.

5.2.20. **build/tmp/work/**

This directory contains architecture-specific work sub-directories for packages built by BitBake. All tasks execute from a work directory. For example, the source for a particular package is unpacked, patched, configured and compiled all within its own work directory. Within the work directory, organization is based on the package group for which the source is being compiled.

It is worth considering the structure of a typical work directory. As an example, consider the `linux-yocto-kernel-3.0` on the machine `qemux86` built within the Yocto Project. For this package, a work directory of `tmp/work/qemux86-poky-linux/linux-yocto-3.0+git1+<...>`, referred to as `WORKDIR`, is created. Within this directory, the source is unpacked to `linux-qemux86-standard-build` and then patched by Quilt (see the "Modifying Package Source Code with Quilt [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#using-a-quilt-workflow>]" section in the Yocto Project Development Manual. Within the `linux-qemux86-standard-build` directory, standard Quilt directories `linux-3.0/patches` and `linux-3.0/.pc` are created, and standard Quilt commands can be used.

There are other directories generated within `WORKDIR`. The most important directory is `WORKDIR/temp/`, which has log files for each task (`log.do_*.pid`) and contains the scripts BitBake runs for each task (`run.do_*.pid`). The `WORKDIR/image/` directory is where "make install" places its output that is then split into sub-packages within `WORKDIR/packages-split/`.

5.3. The Metadata **-meta/**

As mentioned previously, metadata is the core of the Yocto Project. Metadata has several important subdivisions:

5.3.1. **meta/classes/**

This directory contains the *.bbclass files. Class files are used to abstract common code so it can be reused by multiple packages. Every package inherits the base.bbclass file. Examples of other important classes are autotools.bbclass, which in theory allows any Autotool-enabled package to work with the Yocto Project with minimal effort. Another example is kernel.bbclass that contains common code and functions for working with the Linux kernel. Functions like image generation or packaging also have their specific class files such as image.bbclass, rootfs_*.bbclass and package*.bbclass.

5.3.2. **meta/conf/**

This directory contains the core set of configuration files that start from bitbake.conf and from which all other configuration files are included. See the include statements at the end of the file and you will note that even local.conf is loaded from there. While bitbake.conf sets up the defaults, you can often override these by using the (local.conf) file, machine file or the distribution configuration file.

5.3.3. **meta/conf/machine/**

This directory contains all the machine configuration files. If you set MACHINE="qemux86", the OpenEmbedded build system looks for a qemux86.conf file in this directory. The include directory contains various data common to multiple machines. If you want to add support for a new machine to the Yocto Project, look in this directory.

5.3.4. **meta/conf/distro/**

Any distribution-specific configuration is controlled from this directory. For the Yocto Project, the defaultsetup.conf is the main file here. This directory includes the versions and the SRCDATE definitions for applications that are configured here. An example of an alternative configuration might be poky-bleeding.conf. Although this file mainly inherits its configuration from Poky.

5.3.5. **meta/recipes-bsp/**

This directory contains anything linking to specific hardware or hardware configuration information such as "u-boot" and "grub".

5.3.6. **meta/recipes-connectivity/**

This directory contains libraries and applications related to communication with other devices.

5.3.7. **meta/recipes-core/**

This directory contains what is needed to build a basic working Linux image including commonly used dependencies.

5.3.8. **meta/recipes-devtools/**

This directory contains tools that are primarily used by the build system. The tools, however, can also be used on targets.

5.3.9. **meta/recipes-extended/**

This directory contains non-essential applications that add features compared to the alternatives in core. You might need this directory for full tool functionality or for Linux Standard Base (LSB) compliance.

5.3.10. meta/recipes-gnome/

This directory contains all things related to the GTK+ application framework.

5.3.11. meta/recipes-graphics/

This directory contains X and other graphically related system libraries

5.3.12. meta/recipes-kernel/

This directory contains the kernel and generic applications and libraries that have strong kernel dependencies.

5.3.13. meta/recipes-multimedia/

This directory contains codecs and support utilities for audio, images and video.

5.3.14. meta/recipes-qt/

This directory contains all things related to the Qt application framework.

5.3.15. meta/recipes-rt/

This directory contains package and image recipes for using and testing the PREEMPT_RT kernel.

5.3.16. meta/recipes-sato/

This directory contains the Sato demo/reference UI/UX and its associated applications and configuration data.

5.3.17. meta/recipes-support/

This directory contains recipes that used by other recipes, but that are not directly included in images (i.e. dependencies of other recipes).

5.3.18. meta/site/

This directory contains a list of cached results for various architectures. Because certain "autoconf" test results cannot be determined when cross-compiling due to the tests not able to run on a live system, the information in this directory is passed to "autoconf" for the various architectures.

5.3.19. meta/recipes.txt

This file is a description of the contents of recipes-.*.

Chapter 6. BitBake

BitBake is a program written in Python that interprets the metadata used by the OpenEmbedded build system. At some point, developers wonder what actually happens when you enter:

```
$ bitbake core-image-sato
```

This chapter provides an overview of what happens behind the scenes from BitBake's perspective.

Note

BitBake strives to be a generic "task" executor that is capable of handling complex dependency relationships. As such, it has no real knowledge of what the tasks being executed actually do. BitBake just considers a list of tasks with dependencies and handles metadata that consists of variables in a certain format that get passed to the tasks.

6.1. Parsing

BitBake parses configuration files, classes, and `.bb` files.

The first thing BitBake does is look for the `bitbake.conf` file. This file resides in the Source Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#source-directory>] within the `meta/conf/` directory. BitBake finds it by examining its `BBPATH` environment variable and looking for the `meta/conf/` directory.

The `bitbake.conf` file lists other configuration files to include from a `conf/` directory below the directories listed in `BBPATH`. In general, the most important configuration file from a user's perspective is `local.conf`, which contains a user's customized settings for the OpenEmbedded build environment. Other notable configuration files are the distribution configuration file (set by the `DISTRO` variable) and the machine configuration file (set by the `MACHINE` variable). The `DISTRO` and `MACHINE` BitBake environment variables are both usually set in the `local.conf` file. Valid distribution configuration files are available in the `meta/conf/distro/` directory and valid machine configuration files in the `meta/conf/machine/` directory. Within the `meta/conf/machine/include/` directory are various `tune-*.inc` configuration files that provide common "tuning" settings specific to and shared between particular architectures and machines.

After the parsing of the configuration files, some standard classes are included. The base `.bbclass` file is always included. Other classes that are specified in the configuration using the `INHERIT` variable are also included. Class files are searched for in a `classes` subdirectory under the paths in `BBPATH` in the same way as configuration files.

After classes are included, the variable `BBFILES` is set, usually in `local.conf`, and defines the list of places to search for `.bb` files. By default, the `BBFILES` variable specifies the `meta/recipes-*/` directory within Poky. Adding extra content to `BBFILES` is best achieved through the use of BitBake layers as described in the "Understanding and Creating Layers [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#understanding-and-creating-layers>]" section of the Yocto Project Development Manual.

BitBake parses each `.bb` file in `BBFILES` and stores the values of various variables. In summary, for each `.bb` file the configuration plus the base class of variables are set, followed by the data in the `.bb` file itself, followed by any `inherit` commands that `.bb` file might contain.

Because parsing `.bb` files is a time consuming process, a cache is kept to speed up subsequent parsing. This cache is invalid if the timestamp of the `.bb` file itself changes, or if the timestamps of any of the `include`, `configuration` or `class` files the `.bb` file depends on changes.

6.2. Preferences and Providers

Once all the `.bb` files have been parsed, BitBake starts to build the target (`core-image-sato` in the previous section's example) and looks for providers of that target. Once a provider is selected, BitBake resolves all the dependencies for the target. In the case of `core-image-sato`, it would lead to `packagegroup-core-x11-sato`, which in turn leads to recipes like `matchbox-terminal`, `pcmanfm` and `gthumb`. These recipes in turn depend on `eglbc` and the `toolchain`.

Sometimes a target might have multiple providers. A common example is "virtual/kernel", which is provided by each kernel package. Each machine often selects the best kernel provider by using a line similar to the following in the machine configuration file:

```
PREFERRED_PROVIDER_virtual/kernel = "linux-yocto"
```

The default PREFERRED_PROVIDER is the provider with the same name as the target.

Understanding how providers are chosen is made complicated by the fact that multiple versions might exist. BitBake defaults to the highest version of a provider. Version comparisons are made using the same method as Debian. You can use the PREFERRED_VERSION variable to specify a particular version (usually in the distro configuration). You can influence the order by using the DEFAULT_PREFERENCE variable. By default, files have a preference of "0". Setting the DEFAULT_PREFERENCE to "-1" makes the package unlikely to be used unless it is explicitly referenced. Setting the DEFAULT_PREFERENCE to "1" makes it likely the package is used. PREFERRED_VERSION overrides any DEFAULT_PREFERENCE setting. DEFAULT_PREFERENCE is often used to mark newer and more experimental package versions until they have undergone sufficient testing to be considered stable.

In summary, BitBake has created a list of providers, which is prioritized, for each target.

6.3. Dependencies

Each target BitBake builds consists of multiple tasks such as fetch, unpack, patch, configure, and compile. For best performance on multi-core systems, BitBake considers each task as an independent entity with its own set of dependencies.

Dependencies are defined through several variables. You can find information about variables BitBake uses in the BitBake documentation, which is found in the bitbake/doc/manual directory within the Source Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#source-directory>]. At a basic level, it is sufficient to know that BitBake uses the DEPENDS and RDEPENDS variables when calculating dependencies.

6.4. The Task List

Based on the generated list of providers and the dependency information, BitBake can now calculate exactly what tasks it needs to run and in what order it needs to run them. The build now starts with BitBake forking off threads up to the limit set in the BB_NUMBER_THREADS variable. BitBake continues to fork threads as long as there are tasks ready to run, those tasks have all their dependencies met, and the thread threshold has not been exceeded.

It is worth noting that you can greatly speed up the build time by properly setting the BB_NUMBER_THREADS variable. See the "Building an Image [<http://www.yoctoproject.org/docs/1.3/yocto-project-qs/yocto-project-qs.html#building-image>]" section in the Yocto Project Quick Start for more information.

As each task completes, a timestamp is written to the directory specified by the STAMP variable (usually build/tmp/stamps/*). On subsequent runs, BitBake looks at the /build/tmp/stamps directory and does not rerun tasks that are already completed unless a timestamp is found to be invalid. Currently, invalid timestamps are only considered on a per .bb file basis. So, for example, if the configure stamp has a timestamp greater than the compile timestamp for a given target, then the compile task would rerun. Running the compile task again, however, has no effect on other providers that depend on that target. This behavior could change or become configurable in future versions of BitBake.

Note

Some tasks are marked as "nostamp" tasks. No timestamp file is created when these tasks are run. Consequently, "nostamp" tasks are always rerun.

6.5. Running a Task

Tasks can either be a shell task or a Python task. For shell tasks, BitBake writes a shell script to \${WORKDIR}/temp/run.do_taskname.pid and then executes the script. The generated shell script

contains all the exported variables, and the shell functions with all variables expanded. Output from the shell script goes to the file `${WORKDIR}/temp/log.do_taskname.pid`. Looking at the expanded shell functions in the run file and the output in the log files is a useful debugging technique.

For Python tasks, BitBake executes the task internally and logs information to the controlling terminal. Future versions of BitBake will write the functions to files similar to the way shell tasks are handled. Logging will be handled in way similar to shell tasks as well.

Once all the tasks have been completed BitBake exits.

When running a task, BitBake tightly controls the execution environment of the build tasks to make sure unwanted contamination from the build machine cannot influence the build. Consequently, if you do want something to get passed into the build task's environment, you must take a few steps:

1. Tell BitBake to load what you want from the environment into the data store. You can do so through the `BB_ENV_EXTRAWHITE` variable. For example, assume you want to prevent the build system from accessing your `$HOME/.ccache` directory. The following command tells BitBake to load `CCACHE_DIR` from the environment into the data store:

```
export BB_ENV_EXTRAWHITE="$BB_ENV_EXTRAWHITE CCACHE_DIR"
```

2. Tell BitBake to export what you have loaded into the environment store to the task environment of every running task. Loading something from the environment into the data store (previous step) only makes it available in the datastore. To export it to the task environment of every running task, use a command similar to the following in your `local.conf` or distro configuration file:

```
export CCACHE_DIR
```

Note

A side effect of the previous steps is that BitBake records the variable as a dependency of the build process in things like the shared state checksums. If doing so results in unnecessary rebuilds of tasks, you can whitelist the variable so that the shared state code ignores the dependency when it creates checksums. For information on this process, see the `BB_HASHBASE_WHITELIST` example in the "Checksums (Signatures)" section.

6.6. BitBake Command Line

Following is the BitBake help output:

```
$ bitbake --help
Usage: bitbake [options] [package ...]
```

```
Executes the specified task (default is 'build') for a given set of BitBake files.
It expects that BBFILES is defined, which is a space separated list of files to
be executed. BBFILES does support wildcards.
Default BBFILES are the .bb files in the current directory.
```

Options:

```
--version          show program's version number and exit
-h, --help        show this help message and exit
-b BUILDFILE, --buildfile=BUILDFILE
                  execute the task against this .bb file, rather than a
                  package from BBFILES. Does not handle any
                  dependencies.
-k, --continue    continue as much as possible after an error. While the
                  target that failed, and those that depend on it,
                  cannot be remade, the other dependencies of these
                  targets can be processed all the same.
-a, --tryaltconfigs
                  continue with builds by trying to use alternative
                  providers where possible.
```

```

-f, --force           force run of specified cmd, regardless of stamp status
-c CMD, --cmd=CMD    Specify task to execute. Note that this only executes
                    the specified task for the providee and the packages
                    it depends on, i.e. 'compile' does not implicitly call
                    stage for the dependencies (IOW: use only if you know
                    what you are doing). Depending on the base.bbclass a
                    listtasks tasks is defined and will show available
                    tasks
-r PREFILE, --read=PREFILE
                    read the specified file before bitbake.conf
-R POSTFILE, --postread=POSTFILE
                    read the specified file after bitbake.conf
-v, --verbose        output more chit-chat to the terminal
-D, --debug          Increase the debug level. You can specify this more
                    than once.
-n, --dry-run        don't execute, just go through the motions
-S, --dump-signatures
                    don't execute, just dump out the signature
                    construction information
-p, --parse-only     quit after parsing the BB files (developers only)
-s, --show-versions  show current and preferred versions of all packages
-e, --environment    show the global or per-package environment (this is
                    what used to be bbread)
-g, --graphviz       emit the dependency trees of the specified packages in
                    the dot syntax
-I EXTRA_ASSUME_PROVIDED, --ignore-deps=EXTRA_ASSUME_PROVIDED
                    Assume these dependencies don't exist and are already
                    provided (equivalent to ASSUME_PROVIDED). Useful to
                    make dependency graphs more appealing
-l DEBUG_DOMAINS, --log-domains=DEBUG_DOMAINS
                    Show debug logging for the specified logging domains
-P, --profile        profile the command and print a report
-u UI, --ui=UI       userinterface to use
-t SERVERTYPE, --servertime=SERVERTYPE
                    Choose which server to use, none, process or xmlrpc
--revisions-changed Set the exit code depending on whether upstream
                    floating revisions have changed or not

```

6.7. Fetchers

BitBake also contains a set of "fetcher" modules that allow retrieval of source code from various types of sources. For example, BitBake can get source code from a disk with the metadata, from websites, from remote shell accounts or from Source Code Management (SCM) systems like cvs/subversion/git.

Fetchers are usually triggered by entries in SRC_URI. You can find information about the options and formats of entries for specific fetchers in the BitBake manual located in the bitbake/doc/manual directory of the Source Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#source-directory>].

One useful feature for certain Source Code Manager (SCM) fetchers is the ability to "auto-update" when the upstream SCM changes version. Since this ability requires certain functionality from the SCM, not all systems support it. Currently Subversion, Bazaar and to a limited extent, Git support the ability to "auto-update". This feature works using the SRCREV variable. See the "Using an External SCM [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#platdev-appdev-srcrev>]" section in the Yocto Project Development Manual for more information.

Chapter 7. Classes

Class files are used to abstract common functionality and share it amongst multiple `.bb` files. Any metadata usually found in a `.bb` file can also be placed in a class file. Class files are identified by the extension `.bbclass` and are usually placed in a `classes/` directory beneath the `meta*/` directory found in the Source Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#source-directory>]. Class files can also be pointed to by `BUILDDIR` (e.g. `build/`) in the same way as `.conf` files in the `conf` directory. Class files are searched for in `BBPATH` using the same method by which `.conf` files are searched.

In most cases inheriting the class is enough to enable its features, although for some classes you might need to set variables or override some of the default behaviour.

7.1. The base class `-base.bbclass`

The base class is special in that every `.bb` file inherits it automatically. This class contains definitions for standard basic tasks such as fetching, unpacking, configuring (empty by default), compiling (runs any `Makefile` present), installing (empty by default) and packaging (empty by default). These classes are often overridden or extended by other classes such as `autotools.bbclass` or `package.bbclass`. The class also contains some commonly used functions such as `oe_runmake`.

7.2. Autotooled Packages `-autotools.bbclass`

Autotools (`autoconf`, `automake`, and `libtool`) bring standardization. This class defines a set of tasks (`configure`, `compile` etc.) that work for all Autotooled packages. It should usually be enough to define a few standard variables and then simply inherit `autotools`. This class can also work with software that emulates Autotools. For more information, see the "Autotooled Package [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#usingpoky-extend-addpkg-autotools>]" section in the Yocto Project Development Manual.

It's useful to have some idea of how the tasks defined by this class work and what they do behind the scenes.

- `do_configure` # regenerates the `configure` script (using `autoreconf`) and then launches it with a standard set of arguments used during cross-compilation. You can pass additional parameters to `configure` through the `EXTRA_OECONF` variable.
- `do_compile` # runs `make` with arguments that specify the compiler and linker. You can pass additional arguments through the `EXTRA_OEMAKE` variable.
- `do_install` # runs `make install` and passes a `DESTDIR` option, which takes its value from the standard `DESTDIR` variable.

7.3. Alternatives `-update-alternatives.bbclass`

Several programs can fulfill the same or similar function and be installed with the same name. For example, the `ar` command is available from the `busybox`, `binutils` and `elfutils` packages. The `update-alternatives.bbclass` class handles renaming the binaries so that multiple packages can be installed without conflicts. The `ar` command still works regardless of which packages are installed or subsequently removed. The class renames the conflicting binary in each package and symlinks the highest priority binary during installation or removal of packages.

Four variables control this class:

- `ALTERNATIVE_NAME` # The name of the binary that is replaced (`ar` in this example).
- `ALTERNATIVE_LINK` # The path to the resulting binary (`/bin/ar` in this example).
- `ALTERNATIVE_PATH` # The path to the real binary (`/usr/bin/ar.binutils` in this example).

- `ALTERNATIVE_PRIORITY #` The priority of the binary. The version with the most features should have the highest priority.

Currently, the OpenEmbedded build system supports only one binary per package.

7.4. Initscripts -`update-rc.d.bbclass`

This class uses `update-rc.d` to safely install an initialization script on behalf of the package. The OpenEmbedded build system takes care of details such as making sure the script is stopped before a package is removed and started when the package is installed. Three variables control this class: `INITSCRIPT_PACKAGES`, `INITSCRIPT_NAME` and `INITSCRIPT_PARAMS`. See the variable links for details.

7.5. Binary config scripts -`binconfig.bbclass`

Before `pkg-config` had become widespread, libraries shipped shell scripts to give information about the libraries and include paths needed to build software (usually named `LIBNAME-config`). This class assists any recipe using such scripts.

During staging, BitBake installs such scripts into the `sysroots/` directory. BitBake also changes all paths to point into the `sysroots/` directory so all builds that use the script will use the correct directories for the cross compiling layout.

7.6. Debian renaming -`debian.bbclass`

This class renames packages so that they follow the Debian naming policy (i.e. `eglibc` becomes `libc6` and `eglibc-devel` becomes `libc6-dev`).

7.7. Pkg-config -`pkgconfig.bbclass`

`pkg-config` brought standardization and this class aims to make its integration smooth for all libraries that make use of it.

During staging, BitBake installs `pkg-config` data into the `sysroots/` directory. By making use of `sysroot` functionality within `pkg-config`, this class no longer has to manipulate the files.

7.8. Distribution of sources - `src_distribute_local.bbclass`

Many software licenses require that source files be provided along with the binaries. To simplify this process, two classes were created: `src_distribute.bbclass` and `src_distribute_local.bbclass`.

The results of these classes are `tmp/dep/oy/source/` subdirs with sources sorted by `LICENSE` field. If recipes list few licenses (or have entries like "Bitstream Vera"), the source archive is placed in each license directory.

This class operates using three modes:

- `copy`: Copies the files to the distribute directory.
- `symlink`: Symlinks the files to the distribute directory.
- `move+symlink`: Moves the files into the distribute directory and then symlinks them back.

7.9. Perl modules -`cpan.bbclass`

Recipes for Perl modules are simple. These recipes usually only need to point to the source's archive and then inherit the proper `.bbclass` file. Building is split into two methods depending on which method the module authors used.

Modules that use old `Makefile.PL`-based build system require `cpan.bbclass` in their recipes.

Modules that use `Build.PL`-based build system require using `cpan_build.bbclass` in their recipes.

7.10. Python extensions -**distutils.bbclass**

Recipes for Python extensions are simple. These recipes usually only need to point to the source's archive and then inherit the proper `.bbclass` file. Building is split into two methods depending on which method the module authors used.

Extensions that use an Autotools-based build system require Autotools and `distutils`-based `.bbclass` files in their recipes.

Extensions that use `distutils`-based build systems require `distutils.bbclass` in their recipes.

7.11. Developer Shell -**devshell.bbclass**

This class adds the `devshell` task. Distribution policy dictates whether to include this class. See the "Using a Development Shell [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#platdev-appdev-devshell>]" section in the Yocto Project Development Manual for more information about using `devshell`.

7.12. Package Groups -**packagegroup.bbclass**

This class sets default values appropriate for package group recipes (such as `PACKAGES`, `PACKAGE_ARCH`, `ALLOW_EMPTY`, and so forth). It is highly recommended that all package group recipes inherit this class.

For information on how to use this class, see the "Customizing Images Using Custom Package Tasks [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#usingpoky-extend-customimage-customtasks>]" section in the Yocto Project Development Manual.

Previously, this class was named `task.bbclass`.

7.13. Packaging -**package*.bbclass**

The packaging classes add support for generating packages from a build's output. The core generic functionality is in `package.bbclass`. The code specific to particular package types is contained in various sub-classes such as `package_deb.bbclass`, `package_ipk.bbclass`, and `package_rpm.bbclass`. Most users will want one or more of these classes.

You can control the list of resulting package formats by using the `PACKAGE_CLASSES` variable defined in the `local.conf` configuration file, which is located in the `conf` folder of the Source Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#source-directory>]. When defining the variable, you can specify one or more package types. Since images are generated from packages, a packaging class is needed to enable image generation. The first class listed in this variable is used for image generation.

The package class you choose can affect build-time performance and has space ramifications. In general, building a package with RPM takes about thirty percent more time as compared to using IPK to build the same or similar package. This comparison takes into account a complete build of the package with all dependencies previously built. The reason for this discrepancy is because the RPM package manager creates and processes more metadata than the IPK package manager. Consequently, you might consider setting `PACKAGE_CLASSES` to `"package_ipk"` if you are building smaller systems.

Keep in mind, however, that RPM starts to provide more abilities than IPK due to the fact that it processes more metadata. For example, this information includes individual file types, file checksum generation and evaluation on install, sparse file support, conflict detection and resolution for multilib systems, ACID style upgrade, and repackaging abilities for rollbacks.

Another consideration for packages built using the RPM package manager is space. For smaller systems, the extra space used for the Berkley Database and the amount of metadata can affect your ability to do on-device upgrades.

You can find additional information on the effects of the package class at these two Yocto Project mailing list links:

- <https://lists.yoctoproject.org/pipermail/poky/2011-May/006362.html> [<http://lists.yoctoproject.org/pipermail/poky/2011-May/006362.html>]
- <https://lists.yoctoproject.org/pipermail/poky/2011-May/006363.html> [<http://lists.yoctoproject.org/pipermail/poky/2011-May/006363.html>]

7.14. Building kernels -**kernel.bbclass**

This class handles building Linux kernels. The class contains code to build all kernel trees. All needed headers are staged into the `STAGING_KERNEL_DIR` directory to allow out-of-tree module builds using `module.bbclass`.

This means that each built kernel module is packaged separately and inter-module dependencies are created by parsing the `modinfo` output. If all modules are required, then installing the `kernel-modules` package installs all packages with modules and various other kernel packages such as `kernel-vmlinux`.

Various other classes are used by the kernel and module classes internally including `kernel-arch.bbclass`, `module_strip.bbclass`, `module-base.bbclass`, and `linux-kernel-base.bbclass`.

7.15. Creating images -**image.bbclass** and **rootfs*.bbclass**

These classes add support for creating images in several formats. First, the root filesystem is created from packages using one of the `rootfs_*.bbclass` files (depending on the package format used) and then the image is created.

The `IMAGE_FSTYPES` variable controls the types of images to generate.

The `IMAGE_INSTALL` variable controls the list of packages to install into the image.

7.16. Host System sanity checks -**sanity.bbclass**

This class checks to see if prerequisite software is present so that users can be notified of potential problems that might affect their build. The class also performs basic user configuration checks from the `local.conf` configuration file to prevent common mistakes that cause build failures. Distribution policy usually determines whether to include this class.

7.17. Generated output quality assurance checks - **insane.bbclass**

This class adds a step to the package generation process that sanity checks the packages generated by the OpenEmbedded build system. A range of checks are performed that check the build's output for common problems that show up during runtime. Distribution policy usually dictates whether to include this class.

You can configure the sanity checks so that specific test failures either raise a warning or an error message. Typically, failures for new tests generate a warning. Subsequent failures for the same test would then generate an error message once the metadata is in a known and good condition. You use the `WARN_QA` variable to specify tests for which you want to generate a warning message on failure. You use the `ERROR_QA` variable to specify tests for which you want to generate an error message on failure.

The following list shows the tests you can list with the `WARN_QA` and `ERROR_QA` variables:

- `ldflags`: Ensures that the binaries were linked with the `LDFLAGS` options provided by the build system. If this test fails, check that the `LDFLAGS` variable is being passed to the linker command.
- `useless-rpaths`: Checks for dynamic library load paths (`rpaths`) in the binaries that by default on a standard system are searched by the linker (e.g. `/lib` and `/usr/lib`). While these paths will not cause any breakage, they do waste space and are unnecessary.

- `rpaths`: Checks for `rpaths` in the binaries that contain build system paths such as `TMPDIR`. If this test fails, bad `-rpath` options are being passed to the linker commands and your binaries have potential security issues.
- `dev-so`: Checks that the `.so` symbolic links are in the `-dev` package and not in any of the other packages. In general, these symlinks are only useful for development purposes. Thus, the `-dev` package is the correct location for them. Some very rare cases do exist for dynamically loaded modules where these symlinks are needed instead in the main package.
- `debug-files`: Checks for `.debug` directories in anything but the `-dbg` package. The debug files should all be in the `-dbg` package. Thus, anything packaged elsewhere is incorrect packaging.
- `arch`: Checks the Executable and Linkable Format (ELF) type, bit size and endianness of any binaries to ensure it matches the target architecture. This test fails if any binaries don't match the type since there would be an incompatibility. Sometimes software, like bootloaders, might need to bypass this check.
- `debug-deps`: Checks that `-dbg` packages only depend on other `-dbg` packages and not on any other types of packages, which would cause a packaging bug.
- `dev-deps`: Checks that `-dev` packages only depend on other `-dev` packages and not on any other types of packages, which would be a packaging bug.
- `pkgconfig`: Checks `.pc` files for any `TMPDIR`/`WORKDIR` paths. Any `.pc` file containing these paths is incorrect since `pkg-config` itself adds the correct `sysroot` prefix when the files are accessed.
- `la`: Checks `.la` files for any `TMPDIR` paths. Any `.la` file containing these paths is incorrect since `libtool` adds the correct `sysroot` prefix when using the files automatically itself.
- `desktop`: Runs the `desktop-file-validate` program against any `.desktop` files to validate their contents against the specification for `.desktop` files.

7.18. Autotools configuration data cache - `siteinfo.bbclass`

Autotools can require tests that must execute on the target hardware. Since this is not possible in general when cross compiling, site information is used to provide cached test results so these tests can be skipped over but still make the correct values available. The `meta/site` directory contains test results sorted into different categories such as architecture, endianness, and the `libc` used. Site information provides a list of files containing data relevant to the current build in the `CONFIG_SITE` variable that Autotools automatically picks up.

The class also provides variables like `SITEINFO_ENDIANNESS` and `SITEINFO_BITS` that can be used elsewhere in the metadata.

Because this class is included from `base.bbclass`, it is always active.

7.19. Adding Users - `useradd.bbclass`

If you have packages that install files that are owned by custom users or groups, you can use this class to specify those packages and associate the users and groups with those packages. The `meta-skeleton/recipes-skeleton/useradd/useradd-example.bb` recipe in the Source Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#source-directory>] provides a simple example that shows how to add three users and groups to two packages. See the `useradd-example.bb` for more information on how to use this class.

7.20. Using External Source - `externalsrc.bbclass`

You can use this class to build software from source code that is external to the OpenEmbedded build system. In other words, your source code resides in an external tree outside of the Yocto Project.

Building software from an external source tree means that the normal fetch, unpack, and patch process is not used.

To use the class, you need to define the `S` variable to point to the directory that contains the source files. You also need to have your recipe inherit the `externalsrc.bbclass` class.

This class expects the source code to support recipe builds that use the `B` variable to point to the directory in which the OpenEmbedded build system places the generated objects built from the recipes. By default, the `B` directory is set to the following, which is separate from the Source Directory (`S`):

```
${WORKDIR}/${BPN}-${PV}/
```

See the glossary entries for the `WORKDIR`, `BPN`, `PV`, `S`, and `B` for more information.

You can build object files in the external tree by setting the `B` variable equal to `"${S}"`. However, this practice does not work well if you use the source for more than one variant (i.e., "natives" such as `quilt-native`, or "crosses" such as `gcc-cross`). So, be sure there are no "native", "cross", or "multilib" variants of the recipe.

If you do want to build different variants of a recipe, you can use the `BBCLASSEXTEND` variable. When you do, the `B` variable must support the recipe's ability to build variants in different working directories. Most autotools-based recipes support separating these directories. The OpenEmbedded build system defaults to using separate directories for `gcc` and some kernel recipes. Alternatively, you can make sure that separate recipes exist that each use the `BBCLASSEXTEND` variable to build each variant. The separate recipes can inherit a single target recipe.

For information on how to use this class, see the "Building Software from an External Source [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#building-software-from-an-external-source>]" section in the Yocto Project Development Manual.

7.21. Other Classes

Thus far, this chapter has discussed only the most useful and important classes. However, other classes exist within the `meta/classes` directory in the Source Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#source-directory>]. You can examine the `.bbclass` files directly for more information.

Chapter 8. Images

The OpenEmbedded build process supports several types of images to satisfy different needs. When you issue the `bitbake` command you provide a “top-level” recipe that essentially begins the build for the type of image you want.

Note

Building an image without GNU General Public License Version 3 (GPLv3) components is only supported for minimal and base images. Furthermore, if you are going to build an image using non-GPLv3 components, you must make the following changes in the `local.conf` file before using the `BitBake` command to build the minimal or base image:

1. Comment out the `EXTRA_IMAGE_FEATURES` line
2. Set `INCOMPATIBLE_LICENSE = "GPLv3"`

From within the poky Git repository, use the following command to list the supported images:

```
$ ls meta*/recipes*/images/*.bb
```

These recipes reside in the `meta/recipes-core/images`, `meta/recipes-extended/images`, `meta/recipes-graphics/images`, and `meta/recipes-sato/images` directories within the source directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#source-directory>]. Although the recipe names are somewhat explanatory, here is a list that describes them:

- `core-image-base`: A console-only image that fully supports the target device hardware.
- `core-image-minimal`: A small image just capable of allowing a device to boot.
- `core-image-minimal-dev`: A `core-image-minimal` image suitable for development work using the host. The image includes headers and libraries you can use in a host development environment.
- `core-image-minimal-initramfs`: A `core-image-minimal` image that has the Minimal RAM-based Initial Root Filesystem (`initramfs`) as part of the kernel, which allows the system to find the first “init” program more efficiently.
- `core-image-minimal-mtdutils`: A `core-image-minimal` image that has support for the Minimal MTD Utilities, which let the user interact with the MTD subsystem in the kernel to perform operations on flash devices.
- `core-image-x11`: A very basic X11 image with a terminal.
- `core-image-basic`: A console-only image with more full-featured Linux system functionality installed.
- `core-image-lsb`: An image that conforms to the Linux Standard Base (LSB) specification.
- `core-image-lsb-dev`: A `core-image-lsb` image that is suitable for development work using the host. The image includes headers and libraries you can use in a host development environment.
- `core-image-lsb-sdk`: A `core-image-lsb` that includes everything in `meta-toolchain` but also includes development headers and libraries to form a complete standalone SDK. This image is suitable for development using the target.
- `core-image-clutter`: An image with support for the Open GL-based toolkit Clutter, which enables development of rich and animated graphical user interfaces.
- `core-image-sato`: An image with Sato support, a mobile environment and visual style that works well with mobile devices. The image supports X11 with a Sato theme and applications such as a terminal, editor, file manager, media player, and so forth.
- `core-image-sato-dev`: A `core-image-sato` image suitable for development using the host. The image includes libraries needed to build applications on the device itself, testing and profiling tools, and debug symbols. This image was formerly `core-image-sdk`.

- `core-image-sato-sdk`: A `core-image-sato` image that includes everything in `meta-toolchain`. The image also includes development headers and libraries to form a complete standalone SDK and is suitable for development using the target.
- `core-image-rt`: A `core-image-minimal` image plus a real-time test suite and tools appropriate for real-time use.
- `core-image-rt-sdk`: A `core-image-rt` image that includes everything in `meta-toolchain`. The image also includes development headers and libraries to form a complete stand-alone SDK and is suitable for development using the target.
- `core-image-gtk-directfb`: An image that uses `gtk+` over `directfb` instead of `X11`. In order to build, this image requires specific distro configuration that enables `gtk` over `directfb`.
- `build-appliance-image`: An image you can boot and run using either the VMware Player [<http://www.vmware.com/products/player/overview.html>] or VMware Workstation [<http://www.vmware.com/products/workstation/overview.html>]. For more information on this image, see the Build Appliance [<http://www.yoctoproject.org/documentation/build-appliance>] page on the Yocto Project website.

Tip

From the Yocto Project release 1.1 onwards, `-live` and `-directdisk` images have been replaced by a "live" option in `IMAGE_FSTYPES` that will work with any image to produce an image file that can be copied directly to a CD or USB device and run as is. To build a live image, simply add "live" to `IMAGE_FSTYPES` within the `local.conf` file or wherever appropriate and then build the desired image as normal.

Chapter 9. Reference: Features

Features provide a mechanism for working out which packages should be included in the generated images. Distributions can select which features they want to support through the `DISTRO_FEATURES` variable, which is set in the `poky.conf` distribution configuration file. Machine features are set in the `MACHINE_FEATURES` variable, which is set in the machine configuration file and specifies the hardware features for a given machine.

These two variables combine to work out which kernel modules, utilities, and other packages to include. A given distribution can support a selected subset of features so some machine features might not be included if the distribution itself does not support them.

9.1. Distro

The items below are features you can use with `DISTRO_FEATURES`. This list only represents features as shipped with the Yocto Project metadata:

- `alsa`: ALSA support will be included (OSS compatibility kernel modules will be installed if available).
- `bluetooth`: Include bluetooth support (integrated BT only)
- `ext2`: Include tools for supporting for devices with internal HDD/Microdrive for storing files (instead of Flash only devices)
- `irda`: Include Irda support
- `keyboard`: Include keyboard support (e.g. keymaps will be loaded during boot).
- `pci`: Include PCI bus support
- `pcmcia`: Include PCMCIA/CompactFlash support
- `usb gadget`: USB Gadget Device support (for USB networking/serial/storage)
- `usb host`: USB Host support (allows to connect external keyboard, mouse, storage, network etc)
- `wifi`: WiFi support (integrated only)
- `cramfs`: CramFS support
- `ipsec`: IPSec support
- `ipv6`: IPv6 support
- `nfs`: NFS client support (for mounting NFS exports on device)
- `ppp`: PPP dialup support
- `smbfs`: SMB networks client support (for mounting Samba/Microsoft Windows shares on device)

9.2. Machine

The items below are features you can use with `MACHINE_FEATURES`. This list only represents features as shipped with the Yocto Project metadata:

- `acpi`: Hardware has ACPI (x86/x86_64 only)
- `alsa`: Hardware has ALSA audio drivers
- `apm`: Hardware uses APM (or APM emulation)
- `bluetooth`: Hardware has integrated BT
- `ext2`: Hardware HDD or Microdrive
- `irda`: Hardware has Irda support

- keyboard: Hardware has a keyboard
- pci: Hardware has a PCI bus
- pcmcia: Hardware has PCMCIA or CompactFlash sockets
- screen: Hardware has a screen
- serial: Hardware has serial support (usually RS232)
- touchscreen: Hardware has a touchscreen
- usb gadget: Hardware is USB gadget device capable
- usb host: Hardware is USB Host capable
- wifi: Hardware has integrated WiFi

9.3. Images

The contents of images generated by the OpenEmbedded build system can be controlled by the `IMAGE_FEATURES` and `EXTRA_IMAGE_FEATURES` variables that you typically configure in your image recipes. Through these variables you can add several different predefined packages such as development utilities or packages with debug information needed to investigate application problems or profile applications.

Current list of `IMAGE_FEATURES` contains the following:

- splash: Enables showing a splash screen during boot. By default, this screen is provided by `psplash`, which does allow customization. If you prefer to use an alternative splash screen package, you can do so by setting the `SPLASH` variable to a different package name (or names) within the image recipe or at the distro configuration level.
- ssh-server-dropbear: Installs the Dropbear minimal SSH server.
- ssh-server-openssh: Installs the OpenSSH SSH server, which is more full-featured than Dropbear. Note that if both the OpenSSH SSH server and the Dropbear minimal SSH server are present in `IMAGE_FEATURES`, then OpenSSH will take precedence and Dropbear will not be installed.
- x11: Installs the X server
- x11-base: Installs the X server with a minimal environment.
- x11-sato: Installs the OpenedHand Sato environment.
- tools-sdk: Installs a full SDK that runs on the device.
- tools-debug: Installs debugging tools such as `strace` and `gdb`.
- tools-profile: Installs profiling tools such as `oprofile`, `exmap`, and `LTTng`.
- tools-testapps: Installs device testing tools (e.g. touchscreen debugging).
- nfs-server: Installs an NFS server.
- dev-pkgs: Installs development packages (headers and extra library links) for all packages installed in a given image.
- staticdev-pkgs: Installs static development packages (i.e. static libraries containing *.a files) for all packages installed in a given image.
- dbg-pkgs: Installs debug symbol packages for all packages installed in a given image.
- doc-pkgs: Installs documentation packages for all packages installed in a given image.

9.4. Feature Backfilling

Sometimes it is necessary in the OpenEmbedded build system to extend `MACHINE_FEATURES` or `DISTRO_FEATURES` to control functionality that was previously enabled and not able to be disabled.

For these cases, we need to add an additional feature item to appear in one of these variables, but we do not want to force developers who have existing values of the variables in their configuration to add the new feature in order to retain the same overall level of functionality. Thus, the OpenEmbedded build system has a mechanism to automatically "backfill" these added features into existing distro or machine configurations. You can see the list of features for which this is done by finding the `DISTRO_FEATURES_BACKFILL` and `MACHINE_FEATURES_BACKFILL` variables in the `meta/conf/bitbake.conf` file.

Because such features are backfilled by default into all configurations as described in the previous paragraph, developers who wish to disable the new features need to be able to selectively prevent the backfilling from occurring. They can do this by adding the undesired feature or features to the `DISTRO_FEATURES_BACKFILL_CONSIDERED` or `MACHINE_FEATURES_BACKFILL_CONSIDERED` variables for distro features and machine features respectively.

Here are two examples to help illustrate feature backfilling:

- The "pulseaudio" distro feature option: Previously, PulseAudio support was enabled within the Qt and GStreamer frameworks. Because of this, the feature is backfilled and thus enabled for all distros through the `DISTRO_FEATURES_BACKFILL` variable in the `meta/conf/bitbake.conf` file. However, your distro needs to disable the feature. You can disable the feature without affecting other existing distro configurations that need PulseAudio support by adding "pulseaudio" to `DISTRO_FEATURES_BACKFILL_CONSIDERED` in your distro's `.conf` file. Adding the feature to this variable when it also exists in the `DISTRO_FEATURES_BACKFILL` variable prevents the build system from adding the feature to your configuration's `DISTRO_FEATURES`, effectively disabling the feature for that particular distro.
- The "rtc" machine feature option: Previously, real time clock (RTC) support was enabled for all target devices. Because of this, the feature is backfilled and thus enabled for all machines through the `MACHINE_FEATURES_BACKFILL` variable in the `meta/conf/bitbake.conf` file. However, your target device does not have this capability. You can disable RTC support for your device without affecting other machines that need RTC support by adding the feature to your machine's `MACHINE_FEATURES_BACKFILL_CONSIDERED` list in the machine's `.conf` file. Adding the feature to this variable when it also exists in the `MACHINE_FEATURES_BACKFILL` variable prevents the build system from adding the feature to your configuration's `MACHINE_FEATURES`, effectively disabling RTC support for that particular machine.

Chapter 10. Variables Glossary

This chapter lists common variables used in the OpenEmbedded build system and gives an overview of their function and contents.

Glossary

A B C D E F H I K L M P R S T W

A

ALLOW_EMPTY Specifies if an output package should still be produced if it is empty. By default, BitBake does not produce empty packages. This default behavior can cause issues when there is an RDEPENDS or some other runtime hard-requirement on the existence of the package.

Like all package-controlling variables, you must always use them in conjunction with a package name override. Here is an example:

```
ALLOW_EMPTY_${PN} = "1"
```

AUTHOR The email address used to contact the original author or authors in order to send patches, forward bugs, etc.

AUTOREV When SRCREV is set to the value of this variable, it specifies that the latest source revision in the repository should be used. Here is an example:

```
SRCREV = "${AUTOREV}"
```

B

B The Build Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#build-directory>]. The OpenEmbedded build system places generated objects into the Build Directory during a recipe's build process. By default, this directory is the same as the S directory:

```
B = ${WORKDIR}/${BPN}-${PV}/
```

You can separate the (S) directory and the directory pointed to by the B variable. Most autotools-based recipes support separating these directories. The build system defaults to using separate directories for gcc and some kernel recipes.

BAD_RECOMMENDATIONS A list of packages not to install despite being recommended by a recipe. Support for this variable exists only when using the ipk packaging backend.

BBCLASSEXTEND Allows you to extend a recipe so that it builds variants of the software. Common variants for recipes exist such as "natives" like quilt-native, which is a copy of quilt built to run on the build system; "crosses" such as gcc-cross, which is a compiler built to run on the build machine but produces binaries that run on the target MACHINE; "nativesdk", which targets the SDK machine instead of MACHINE; and "multilibs" in the form "multilib:<multilib_name>".

To build a different variant of the recipe with a minimal amount of code, it usually is as simple as adding the following to your recipe:

```
BBCLASSEXTEND += "native nativesdk"
BBCLASSEXTEND += "multilib:<multilib_name>"
```

BBMASK

Prevents BitBake from processing recipes and recipe append files. You can use the `BBMASK` variable to "hide" these `.bb` and `.bbappend` files. BitBake ignores any recipe or recipe append files that match the expression. It is as if BitBake does not see them at all. Consequently, matching files are not parsed or otherwise used by BitBake.

The value you provide is passed to python's regular expression compiler. For complete syntax information, see python's documentation at <http://docs.python.org/release/2.3/lib/re-syntax.html>. The expression is compared against the full paths to the files. For example, the following uses a complete regular expression to tell BitBake to ignore all recipe and recipe append files in the `./meta-ti/recipes-misc/` directory:

```
BBMASK = ".*meta-ti/recipes-misc/"
```

Use the `BBMASK` variable from within the `conf/local.conf` file found in the Build Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#build-directory>].

BB_NUMBER_THREADS

The maximum number of tasks BitBake should run in parallel at any one time. If your host development system supports multiple cores a good rule of thumb is to set this variable to twice the number of cores.

BBFILE_COLLECTIONS

Lists the names of configured layers. These names are used to find the other `BBFILE_*` variables. Typically, each layer will append its name to this variable in its `conf/layer.conf` file.

BBFILE_PATTERN

Variable that expands to match files from `BBFILES` in a particular layer. This variable is used in the `conf/layer.conf` file and must be suffixed with the name of the specific layer (e.g. `BBFILE_PATTERN_emenlow`).

BBFILE_PRIORITY

Assigns the priority for recipe files in each layer.

This variable is useful in situations where the same recipe appears in more than one layer. Setting this variable allows you to prioritize a layer against other layers that contain the same recipe - effectively letting you control the precedence for the multiple layers. The precedence established through this variable stands regardless of a recipe's version (PV variable). For example, a layer that has a recipe with a higher PV value but for which the `BBFILE_PRIORITY` is set to have a lower precedence still has a lower precedence.

A larger value for the `BBFILE_PRIORITY` variable results in a higher precedence. For example, the value 6 has a higher precedence than the value 5. If not specified, the `BBFILE_PRIORITY` variable is set based on layer dependencies (see the `LAYERDEPENDS` variable for more information). The default priority, if unspecified for a layer with no dependencies, is the lowest defined priority + 1 (or 1 if no priorities are defined).

Tip

You can use the command `bitbake-layers show_layers` to list all configured layers along with their priorities.

BBFILES	List of recipe files used by BitBake to build software
BBPATH	Used by BitBake to locate .bbclass and configuration files. This variable is analogous to the PATH variable.
BBINCLUDELOGS	Variable that controls how BitBake displays logs on build failure.
BBLAYERS	Lists the layers to enable during the build. This variable is defined in the bblayers.conf configuration file in the Build Directory [http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#build-directory]. Here is an example:

```
BBLAYERS = " \
/home/scottrif/poky/meta \
/home/scottrif/poky/meta-yocto \
/home/scottrif/poky/meta-yocto-bsp \
/home/scottrif/poky/meta-mykernel \
"
```

This example enables four layers, one of which is a custom, user-defined layer named meta-mykernel.

BP	The base recipe name and version but without any special recipe name suffix (i.e. -native, lib64-, and so forth). BP is comprised of the following:
----	---

```
${BPN} - ${PV}
```

BPN	The bare name of the recipe. This variable is a version of the PN variable but removes common suffixes such as "-native" and "-cross" as well as removes common prefixes such as multilib's "lib64-" and "lib32-". The exact list of suffixes removed is specified by the SPECIAL_PKGSUFFIX variable. The exact list of prefixes removed is specified by the MLPREFIX variable. Prefixes are removed for multilib and nativesdk cases.
-----	--

C

CFLAGS	Flags passed to C compiler for the target system. This variable evaluates to the same as TARGET_CFLAGS.
COMPATIBLE_MACHINE	A regular expression which evaluates to match the machines the recipe works with. It stops recipes being run on machines for which they are not compatible. This is particularly useful with kernels. It also helps to increase parsing speed as further parsing of the recipe is skipped if it is found the current machine is not compatible.
CONFFILES	Identifies editable or configurable files that are part of a package. If the Package Management System (PMS) is being used to update packages on the target system, it is possible that configuration files you have changed after the original installation and that you now want to remain unchanged are overwritten. In other words, editable files might exist in the package that you do not want reset as part of the package update process. You can use the CONFFILES variable to list the files in the package that you wish to prevent the PMS from overwriting during this update process.

To use the CONFFILES variable, provide a package name override that identifies the resulting package. Then, provide a space-separated list of files. Here is an example:

```
CONFFILES_${PN} += "${sysconfdir}/file1 \
${sysconfdir}/file2 ${sysconfdir}/file3"
```

A relationship exists between the CONFFILES and FILES variables. The files listed within CONFFILES must be a subset of the files listed within FILES. Because the configuration files you provide with CONFFILES are simply being identified so that the PMS will not overwrite them, it makes sense that the files must already be included as part of the package through the FILES variable.

Note

When specifying paths as part of the CONFFILES variable, it is good practice to use appropriate path variables. For example, `${sysconfdir}` rather than `/etc` or `${bindir}` rather than `/usr/bin`. You can find a list of these variables at the top of the `/meta/conf/bitbake.conf` file in the Source Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#source-directory>].

CONFIG_SITE	A list of files that contains autoconf test results relevant to the current build. This variable is used by the Autotools utilities when running configure.
CORE_IMAGE_EXTRA_INSTALL	Specifies the list of packages to be added to the image. This variable should only be set in the <code>local.conf</code> configuration file found in the Build Directory [http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#build-directory]. This variable replaces <code>POKY_EXTRA_INSTALL</code> , which is no longer supported.

D

D	The destination directory.
DEBUG_BUILD	Specifies to build packages with debugging information. This influences the value of the <code>SELECTED_OPTIMIZATION</code> variable.
DEBUG_OPTIMIZATION	The options to pass in <code>TARGET_CFLAGS</code> and <code>CFLAGS</code> when compiling a system for debugging. This variable defaults to <code>"-O -fno-omit-frame-pointer -g"</code> .
DEFAULT_PREFERENCE	Specifies the priority of recipes.
DEPENDS	Lists a recipe's build-time dependencies (i.e. other recipe files). The system ensures that all the dependencies listed have been built and have their contents in the appropriate sysroots before the recipe's configure task is executed.
DESCRIPTION	The package description used by package managers. If not set, <code>DESCRIPTION</code> takes the value of the <code>SUMMARY</code> variable.
DESTDIR	the destination directory.
DISTRO	The short name of the distribution. This variable corresponds to a file with the extension <code>.conf</code> located in a <code>conf/distro</code> directory within the metadata that contains the distribution configuration. The value must not contain spaces, and is typically all lower-case. If the variable is blank, a set of default configuration will be used, which is specified within <code>meta/conf/distro/defaultsetup.conf</code> .

DISTRO_EXTRA_RDEPENDS	Specifies a list of distro-specific packages to add to all images. This variable takes affect through packagegroup-base so the variable only really applies to the more full-featured images that include packagegroup-base. You can use this variable to keep distro policy out of generic images. As with all other distro variables, you set this variable in the distro .conf file.
DISTRO_EXTRA_RRECOMMENDS	Specifies a list of distro-specific packages to add to all images if the packages exist. The packages might not exist or be empty (e.g. kernel modules). The list of packages are automatically installed but can be removed by the user.
DISTRO_FEATURES	The features enabled for the distribution. For a list of features supported by the Yocto Project as shipped, see the "Distro" section.
DISTRO_FEATURES_BACKFILL	Features to be added to DISTRO_FEATURES if not also present in DISTRO_FEATURES_BACKFILL_CONSIDERED. This variable is set in the meta/conf/bitbake.conf file. It is not intended to be user-configurable. It is best to just reference the variable to see which distro features are being backfilled for all distro configurations. See the Feature backfilling section for more information.
DISTRO_FEATURES_BACKFILL_CONSIDERED	From DISTRO_FEATURES_BACKFILL that should not be backfilled (i.e. added to DISTRO_FEATURES) during the build. See the "Feature Backfilling" section for more information.
DISTRO_NAME	The long name of the distribution.
DISTRO_PN_ALIAS	Alias names used for the recipe in various Linux distributions. See the "Handling a Package Name Alias [http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#usingpoky-configuring-DISTRO_PN_ALIAS]" section in the Yocto Project Development Manual for more information.
DISTRO_VERSION	the version of the distribution.
DL_DIR	The central download directory used by the build process to store downloads. You can set this directory by defining the DL_DIR variable in the /conf/local.conf file. This directory is self-maintaining and you should not have to touch it. By default, the directory is downloads in the Build Directory [http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#build-directory].

```
#DL_DIR ?= "${TOPDIR}/downloads"
```

To specify a different download directory, simply uncomment the line and provide your directory.

During a first build, the system downloads many different source code tarballs from various upstream projects. Downloading can take a while, particularly if your network connection is slow. Tarballs are all stored in the directory defined by DL_DIR and the build system looks there first to find source tarballs.

Note

When wiping and rebuilding, you can preserve this directory to speed up this part of subsequent builds.

You can safely share this directory between multiple builds on the same development machine. For additional information on how the build process gets source files when working behind a firewall or proxy server, see the "FAQ [75]" chapter.

E

ENABLE_BINARY_LOCALE_GENERATION

Variable that controls which locales for `glibc` are to be generated during the build (useful if the target device has 64Mbytes of RAM or less).

EXTENDPE

Used with file and pathnames to create a prefix for a recipe's version based on the recipe's PE value. If PE is set and greater than zero for a recipe, EXTENDPE becomes that value (e.g if PE is equal to "1" then EXTENDPE becomes "1_"). If a recipe's PE is not set (the default) or is equal to zero, EXTENDPE becomes "".

See the STAMP variable for an example.

EXTRA_IMAGE_FEATURES

Allows extra packages to be added to the generated images. You set this variable in the `local.conf` configuration file. Note that some image features are also added using the IMAGE_FEATURES variable generally configured in image recipes. You can use this variable to add more features in addition to those. Here are some examples of features you can add:

"dbg-pkgs" - Adds -dbg packages for all installed packages including symbol information for debugging and profiling.

"dev-pkgs" - Adds -dev packages for all installed packages. This is useful if you want to develop against the libraries in the image.

"tools-sdk" - Adds development tools such as gcc, make, pkgconfig and so forth.

"tools-debug" - Adds debugging tools such as gdb and strace.

"tools-profile" - Adds profiling tools such as oprofile, exmap, lttng and valgrind (x86 only).

"tools-testapps" - Adds useful testing tools such as ts_print, aplay, arecord and so forth.

"debug-tweaks" - Makes an image suitable for development. For example, ssh root access has a blank password. You should remove this feature before you produce a production image.

There are other valid features too, see the Images section for more details.

EXTRA_IMAGEDEPENDS

A list of recipes to be built that do not provide packages to be installed in the root filesystem.

Sometimes a recipe is required to build the final image but is not needed in the root filesystem. You can use the EXTRA_IMAGEDEPENDS variable to list these recipes and thus, specify the dependencies. A typical example is a required bootloader in a machine configuration.

Note

To add packages to the root filesystem, see the various *DEPENDS and *RECOMMENDS variables.

EXTRA_OECMAKE	Additional cmake options.
EXTRA_OECONF	Additional configure script options.
EXTRA_OEMAKE	Additional GNU make options.

F

FILES	The list of directories or files that are placed in packages.
-------	---

To use the FILES variable, provide a package name override that identifies the resulting package. Then, provide a space-separated list of files or paths that identifies the files you want included as part of the resulting package. Here is an example:

```
FILES_${PN} += "${bindir}/mydir1/ ${bindir}/mydir2/myfile"
```

Note

When specifying paths as part of the FILES variable, it is good practice to use appropriate path variables. For example, `${sysconfdir}` rather than `/etc` or `${bindir}` rather than `/usr/bin`. You can find a list of these variables at the top of the `/meta/conf/bitbake.conf` file in the Source Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#source-directory>].

If some of the files you provide with the FILES variable are editable and you know they should not be overwritten during the package update process by the Package Management System (PMS), you can identify these files so that the PMS will not overwrite them. See the CONFFILES variable for information on how to identify these files to the PMS.

FILESEXTRAPATHS	Extends the search path the OpenEmbedded build system uses when looking for files and patches as it processes recipes. The directories BitBake uses when it processes recipes is defined by the FILESPATH variable. You can add directories to the search path by defining the FILESEXTRAPATHS variable.
-----------------	--

To add paths to the search order, provide a list of directories and separate each path using a colon character as follows:

```
FILESEXTRAPATHS_prepend := "path_1:path_2:path_3:"
```

Typically, you want your directories search first. To make sure that happens, use `_prepend` and the immediate expansion (`:=`) operator as shown in the previous example. Finally, to maintain the integrity of the FILESPATH variable, you must include the appropriate beginning or ending (as needed) colon character.

The FILESEXTRAPATHS variable is intended for use in `.bbappend` files to include any additional files provided in that layer. You typically accomplish this with the following:

```
FILESEXTRAPATHS_prepend := "${THISDIR}/${PN}:"
```

FILESPATH	The default set of directories the OpenEmbedded build system uses when searching for patches and files. During the build process, BitBake searches each directory in FILESPATH in the specified order
-----------	---

when looking for files and patches specified by each file:// URI in a recipe.

The default value for the FILESPATH variable is defined in the base.bbclass class found in meta/classes in the Source Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#source-directory>]:

```
FILESPATH = "${@base_set_files_path([ "${FILE_DIRNAME}/${PF}", \
    "${FILE_DIRNAME}/${P}", "${FILE_DIRNAME}/${PN}", \
    "${FILE_DIRNAME}/${BP}", "${FILE_DIRNAME}/${BPN}", \
    "${FILE_DIRNAME}/files", "${FILE_DIRNAME}" ], d)}
```

Do not hand-edit the FILESPATH variable. If you want to extend the set of pathnames that BitBake uses when searching for files and patches, use the FILESEXPATHS variable.

FILESYSTEM_PERMS_TABLES

Allows you to define your own file permissions settings table as part of your configuration for the packaging process. For example, suppose you need a consistent set of custom permissions for a set of groups and users across an entire work project. It is best to do this in the packages themselves but this is not always possible.

By default, the OpenEmbedded build system uses the fs-perms.txt, which is located in the meta/files folder in the Source Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#source-directory>]. If you create your own file permissions setting table, you should place it in your layer or the distros layer.

You define the FILESYSTEM_PERMS_TABLES variable in the conf/local.conf file, which is found in the Build Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#build-directory>], to point to your custom fs-perms.txt. You can specify more than a single file permissions setting table. The paths you specify to these files must be defined within the BBPATH variable.

For guidance on how to create your own file permissions settings table file, examine the existing fs-perms.txt.

FULL_OPTIMIZATION

The options to pass in TARGET_CFLAGS and CFLAGS when compiling an optimized system. This variable defaults to "-fexpensive-optimizations -fomit-frame-pointer -frename-registers -O2".

H

HOMEPAGE

Website where more information about the software the recipe is building can be found.

I

IMAGE_FEATURES

The list of features to include in an image. Typically, you configure this variable in an image recipe. Note that you can also add extra features to the image by using the EXTRA_IMAGE_FEATURES variable. See the "Images" section for the full list of features that can be included in images built by the OpenEmbedded build system.

IMAGE_FSTYPES

Formats of root filesystem images that you want to have created.

IMAGE_INSTALL

Specifies the packages to install into an image. The IMAGE_INSTALL variable is a mechanism for an image recipe and you should use it with care to avoid ordering issues.

Image recipes set `IMAGE_INSTALL` to specify the packages to install into an image through `image.bbclass`. Additionally, "helper" classes exist, such as `core-image.bbclass`, that can take `IMAGE_FEATURES` lists and turn these into auto-generated entries in `IMAGE_INSTALL` in addition to its default contents.

Using `IMAGE_INSTALL` with the `+=` operator from the `/conf/local.conf` file or from within an image recipe is not recommended as it can cause ordering issues. Since `core-image.bbclass` sets `IMAGE_INSTALL` to a default value using the `?=` operator, using a `+=` operation against `IMAGE_INSTALL` will result in unexpected behavior when used in `/conf/local.conf`. Furthermore, the same operation from within an image recipe may or may not succeed depending on the specific situation. In both these cases, the behavior is contrary to how most users expect the `+=` operator to work.

When you use this variable, it is best to use it as follows:

```
IMAGE_INSTALL_append = " package-name"
```

Be sure to include the space between the quotation character and the start of the package name.

`IMAGE_OVERHEAD_FACTOR`

Defines a multiplier that the build system applies to the initial image size for cases when the multiplier times the returned disk usage value for the image is greater than the sum of `IMAGE_ROOTFS_SIZE` and `IMAGE_ROOTFS_EXTRA_SPACE`. The result of the multiplier applied to the initial image size creates free disk space in the image as overhead. By default, the build process uses a multiplier of 1.3 for this variable. This default value results in 30% free disk space added to the image when this method is used to determine the final generated image size. You should be aware that post install scripts and the package management system uses disk space inside this overhead area. Consequently, the multiplier does not produce an image with all the theoretical free disk space. See `IMAGE_ROOTFS_SIZE` for information on how the build system determines the overall image size.

The default 30% free disk space typically gives the image enough room to boot and allows for basic post installs while still leaving a small amount of free disk space. If 30% free space is inadequate, you can increase the default value. For example, the following setting gives you 50% free space added to the image:

```
IMAGE_OVERHEAD_FACTOR = "1.5"
```

Alternatively, you can ensure a specific amount of free disk space is added to the image by using `IMAGE_ROOTFS_EXTRA_SPACE` the variable.

`IMAGE_ROOTFS_EXTRA_SPACE`

Defines additional free disk space created in the image in Kbytes. By default, this variable is set to "0". This free disk space is added to the image after the build system determines the image size as described in `IMAGE_ROOTFS_SIZE`.

This variable is particularly useful when you want to ensure that a specific amount of free disk space is available on a device after an image is installed and running. For example, to be sure 5 Gbytes of free disk space is available, set the variable as follows:

```
IMAGE_ROOTFS_EXTRA_SPACE = "5242880"
```

IMAGE_ROOTFS_SIZE

Defines the size in Kbytes for the generated image. The OpenEmbedded build system determines the final size for the generated image using an algorithm that takes into account the initial disk space used for the generated image, a requested size for the image, and requested additional free disk space to be added to the image. Programatically, the build system determines the final size of the generated image as follows:

```
if (image-du * overhead) < rootfs-size:
internal-rootfs-size = rootfs-size + xspace
else:
internal-rootfs-size = (image-du * overhead) + xspace
```

where:

```
image-du = Returned value of the du command on
           the image.
```

```
overhead = IMAGE_OVERHEAD_FACTOR
```

```
rootfs-size = IMAGE_ROOTFS_SIZE
```

```
internal-rootfs-size = Initial root filesystem
                       size before any modifications.
```

```
xspace = IMAGE_ROOTFS_EXTRA_SPACE
```

INC_PR

Helps define the recipe revision for recipes that share a common include file. You can think of this variable as part of the recipe revision as set from within an include file.

Suppose, for example, you have a set of recipes that are used across several projects. And, within each of those recipes the revision (its PR value) is set accordingly. In this case, when the revision of those recipes changes the burden is on you to find all those recipes and be sure that they get changed to reflect the updated version of the recipe. In this scenario, it can get complicated when recipes used in many places and that provide common functionality are upgraded to a new revision.

A more efficient way of dealing with this situation is to set the INC_PR variable inside the include files that the recipes share and then expand the INC_PR variable within the recipes to help define the recipe revision.

The following provides an example that shows how to use the INC_PR variable given a common include file that defines the variable. Once the variable is defined in the include file, you can use the variable to set the PR values in each recipe. You will notice that when you set a recipe's PR you can provide more granular revisioning by appending values to the INC_PR variable:

```
recipes-graphics/xorg-font/xorg-font-common.inc:INC_PR = "r2"
recipes-graphics/xorg-font/encodings_1.0.4.bb:PR = "${INC_PR}.1"
recipes-graphics/xorg-font/font-util_1.3.0.bb:PR = "${INC_PR}.0"
recipes-graphics/xorg-font/font-alias_1.0.3.bb:PR = "${INC_PR}.3"
```

The first line of the example establishes the baseline revision to be used for all recipes that use the include file. The remaining lines in

	the example are from individual recipes and show how the PR value is set.
INHIBIT_PACKAGE_STRIP	Causes the build to not strip binaries in resulting packages.
INHERIT	Causes the named class to be inherited at this point during parsing. The variable is only valid in configuration files.
INITSCRIPT_PACKAGES	A list of the packages that contain initscripts. If multiple packages are specified, you need to append the package name to the other INITSCRIPT_* as an override. This variable is used in recipes when using update-rc.d.bbclass. The variable is optional and defaults to the PN variable.
INITSCRIPT_NAME	The filename of the initscript (as installed to \${etcdir}/init.d). This variable is used in recipes when using update-rc.d.bbclass. The variable is Mandatory.
INITSCRIPT_PARAMS	Specifies the options to pass to update-rc.d. An example is start 99 5 2 . stop 20 0 1 6 ., which gives the script a runlevel of 99, starts the script in initlevels 2 and 5, and stops the script in levels 0, 1 and 6. The variable is mandatory and is used in recipes when using update-rc.d.bbclass.

K

KBRANCH	A regular expression used by the build process to explicitly identify the kernel branch that is validated, patched and configured during a build. The KBRANCH variable is optional. You can use it to trigger checks to ensure the exact kernel branch you want is being used by the build process. Values for this variable are set in the kernel's recipe file and the kernel's append file. For example, if you are using the Yocto Project kernel that is based on the Linux 3.4 kernel, the kernel recipe file is the meta/recipes-kernel/linux/linux-yocto_3.4.bb file. Following is the default value for KBRANCH and the default override for the architectures the Yocto Project supports:
---------	--

```
KBRANCH_DEFAULT = "standard/base"
KBRANCH = "${KBRANCH_DEFAULT}"
```

This branch exists in the linux-yocto-3.4 kernel Git repository <http://git.yoctoproject.org/cgit.cgi/linux-yocto-3.4/refs/heads>.

This variable is also used from the kernel's append file to identify the kernel branch specific to a particular machine or target hardware. The kernel's append file is located in the BSP layer for a given machine. For example, the kernel append file for the Crown Bay BSP is in the meta-intel Git repository and is named meta-crownbay/recipes-kernel/linux/linux-yocto_3.4.bbappend. Here are the related statements from the append file:

```
COMPATIBLE_MACHINE_crownbay = "crownbay"
KMACHINE_crownbay = "crownbay"
KBRANCH_crownbay = "standard/crownbay"
```

```
COMPATIBLE_MACHINE_crownbay-noemgd = "crownbay-noemgd"
```

```
KMACHINE_crownbay-noemgd = "crownbay"
KBRANCH_crownbay-noemgd = "standard/crownbay"
```

The KBRANCH_* statements identify the kernel branch to use when building for the Crown Bay BSP. In this case there are two identical statements: one for each type of Crown Bay machine.

KERNEL_FEATURES

Includes additional metadata from the Yocto Project kernel Git repository. In the OpenEmbedded build system, the default Board Support Packages (BSPs) metadata is provided through the KMACHINE and KBRANCH variables. You can use the KERNEL_FEATURES variable to further add metadata for all BSPs.

The metadata you add through this variable includes config fragments and features descriptions, which usually includes patches as well as config fragments. You typically override the KERNEL_FEATURES variable for a specific machine. In this way, you can provide validated, but optional, sets of kernel configurations and features.

For example, the following adds netfilter to all the Yocto Project kernels and adds sound support to the qemu86 machine:

```
# Add netfilter to all linux-yocto kernels
KERNEL_FEATURES="features/netfilter"

# Add sound support to the qemu86 machine
KERNEL_FEATURES_append_qemu86=" cfg/sound"
```

KERNEL_IMAGETYPE

The type of kernel to build for a device, usually set by the machine configuration files and defaults to "zImage". This variable is used when building the kernel and is passed to make as the target to build.

KMACHINE

The machine as known by the kernel. Sometimes the machine name used by the kernel does not match the machine name used by the OpenEmbedded build system. For example, the machine name that the OpenEmbedded build system understands as qemuarm goes by a different name in the Linux Yocto kernel. The kernel understands that machine as arm_versatile926ejs. For cases like these, the KMACHINE variable maps the kernel machine name to the OpenEmbedded build system machine name.

Kernel machine names are initially defined in the Yocto Linux Kernel [<http://git.yoctoproject.org/cgit.cgi>] in the meta branch. From the meta branch, look in the meta/cfg/kernel-cache/bsp/<bsp_name>/<bsp_name>-<kernel-type>.scc file. For example, from the meta branch in the linux-yocto-3.0 kernel, the meta/cfg/kernel-cache/bsp/cedartrail/cedartrail-standard.scc file has the following:

```
define KMACHINE cedartrail
define KTYPE standard
define KARCH i386

include ktypes/standard
branch cedartrail

include cedartrail.scc
```

You can see that the kernel understands the machine name for the Cedar Trail BSP as cedartrail.

If you look in the Cedar Trail BSP layer in the meta-intel source repository at meta-cedartrail/recipes-kernel/linux/linux-yocto_3.0.bbappend, you will find the following statements among others:

```
COMPATIBLE_MACHINE_cedartrail = "cedartrail"
KMACHINE_cedartrail = "cedartrail"
KBRANCH_cedartrail = "yocto/standard/cedartrail"
KERNEL_FEATURES_append_cedartrail += "bsp/cedartrail/cedartrail-p
KERNEL_FEATURES_append_cedartrail += "cfg/efi-ext.scc"

COMPATIBLE_MACHINE_cedartrail-nopvr = "cedartrail"
KMACHINE_cedartrail-nopvr = "cedartrail"
KBRANCH_cedartrail-nopvr = "yocto/standard/cedartrail"
KERNEL_FEATURES_append_cedartrail-nopvr += " cfg/smp.scc"
```

The KMACHINE statements in the kernel's append file make sure that the OpenEmbedded build system and the Yocto Linux kernel understand the same machine names.

This append file uses two KMACHINE statements. The first is not really necessary but does ensure that the machine known to the OpenEmbedded build system as cedartrail maps to the machine in the kernel also known as cedartrail:

```
KMACHINE_cedartrail = "cedartrail"
```

The second statement is a good example of why the KMACHINE variable is needed. In this example, the OpenEmbedded build system uses the cedartrail-nopvr machine name to refer to the Cedar Trail BSP that does not support the proprietary PowerVR driver. The kernel, however, uses the machine name cedartrail. Thus, the append file must map the cedartrail-nopvr machine name to the kernel's cedartrail name:

```
KMACHINE_cedartrail-nopvr = "cedartrail"
```

BSPs that ship with the Yocto Project release provide all mappings between the Yocto Project kernel machine names and the OpenEmbedded machine names. Be sure to use the KMACHINE if you create a BSP and the machine name you use is different than that used in the kernel.

L

LAYERDEPENDS

Lists the layers that this recipe depends upon, separated by spaces. Optionally, you can specify a specific layer version for a dependency by adding it to the end of the layer name with a colon, (e.g. "anotherlayer:3" to be compared against LAYERVERSION_anotherlayer in this case). An error will be produced if any dependency is missing or the version numbers do not match exactly (if specified). This variable is used in the conf/layer.conf file and must be suffixed with the name of the specific layer (e.g. LAYERDEPENDS_mylayer).

LAYERDIR

When used inside the layer.conf configuration file, this variable provides the path of the current layer. This variable requires immediate expansion (see the BitBake manual) as lazy expansion

	can result in the expansion happening in the wrong directory and therefore giving the wrong value.
LAYERVERSION	Optionally specifies the version of a layer as a single number. You can use this within LAYERDEPENDS for another layer in order to depend on a specific version of the layer. This variable is used in the conf/layer.conf file and must be suffixed with the name of the specific layer (e.g. LAYERVERSION_mylayer).
LIC_FILES_CHKSUM	Checksums of the license text in the recipe source code. This variable tracks changes in license text of the source code files. If the license text is changed, it will trigger a build failure, which gives the developer an opportunity to review any license change. This variable must be defined for all recipes (unless LICENSE is set to "CLOSED") For more information, see the Tracking License Changes section
LICENSE	The list of source licenses for the recipe. Follow these rules: <ul style="list-style-type: none"> • Do not use spaces within individual license names. • Separate license names using (pipe) when there is a choice between licenses. • Separate license names using & (ampersand) when multiple licenses exist that cover different parts of the source. • You can use spaces between license names. Here are some examples: <pre style="margin-left: 40px;">LICENSE = "LGPLv2.1 GPLv3" LICENSE = "MPL-1 & LGPLv2.1" LICENSE = "GPLv2+"</pre> <p>The first example is from the recipes for Qt, which the user may choose to distribute under either the LGPL version 2.1 or GPL version 3. The second example is from Cairo where two licenses cover different parts of the source code. The final example is from sysstat, which presents a single license.</p>
LICENSE_PATH	Path to additional licenses used during the build. By default, the OpenEmbedded build system uses COMMON_LICENSE_DIR to define the directory that holds common license text used during the build. The LICENSE_PATH variable allows you to extend that location to other areas that have additional licenses: <pre style="margin-left: 40px;">LICENSE_PATH += "/path/to/additional/common/licenses"</pre>

M

MACHINE	Specifies the target device for which the image is built. You define MACHINE in the local.conf file found in the Build Directory [http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#build-directory]. By default, MACHINE is set to "qemux86", which is an x86-based architecture machine to be emulated using QEMU: <pre style="margin-left: 40px;">MACHINE ?= "qemux86"</pre>
---------	---

The variable corresponds to a machine configuration file of the same name, through which machine-specific configurations are set. Thus, when `MACHINE` is set to "qemux86" there exists the corresponding `qemux86.conf` machine configuration file, which can be found in the Source Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#source-directory>] in `meta/conf/machine`.

The list of machines supported by the Yocto Project as shipped include the following:

```
MACHINE ?= "qemuarm"
MACHINE ?= "qemumips"
MACHINE ?= "qemuappc"
MACHINE ?= "qemux86"
MACHINE ?= "qemux86-64"
MACHINE ?= "atom-pc"
MACHINE ?= "beagleboard"
MACHINE ?= "mpc8315e-rdb"
MACHINE ?= "routerstationpro"
```

The last four are Yocto Project reference hardware boards, which are provided in the `meta-yocto-bsp` layer.

Note

Adding additional Board Support Package (BSP) layers to your configuration adds new possible settings for `MACHINE`.

`MACHINE_ESSENTIAL_EXTRA_RDEPENDS`

A list of required machine-specific packages to install as part of the image being built. The build process depends on these packages being present. Furthermore, because this is a "machine essential" variable, the list of packages are essential for the machine to boot. The impact of this variable affects images based on `packagegroup-core-boot`, including the `core-image-minimal` image.

This variable is similar to the `MACHINE_ESSENTIAL_EXTRA_RRECOMMENDS` variable with the exception that the image being built has a build dependency on the variable's list of packages. In other words, the image will not build if a file in this list is not found.

As an example, suppose the machine for which you are building requires `example-init` to be run during boot to initialize the hardware. In this case, you would use the following in the machine's `.conf` configuration file:

```
MACHINE_ESSENTIAL_EXTRA_RDEPENDS += "example-init"
```

`MACHINE_ESSENTIAL_EXTRA_RRECOMMENDS`

A list of recommended machine-specific packages to install as part of the image being built. The build process does not depend on these packages being present. However, because this is a "machine essential" variable, the list of packages are essential for the machine to boot. The impact of this variable affects images based on `packagegroup-core-boot`, including the `core-image-minimal` image.

This variable is similar to the `MACHINE_ESSENTIAL_EXTRA_RDEPENDS` variable with the exception that the image being built does not have a build dependency on the variable's list of packages. In other

words, the image will still build if a package in this list is not found. Typically, this variable is used to handle essential kernel modules, whose functionality may be selected to be built into the kernel rather than as a module, in which case a package will not be produced.

Consider an example where you have a custom kernel where a specific touchscreen driver is required for the machine to be usable. However, the driver can be built as a module or into the kernel depending on the kernel configuration. If the driver is built as a module, you want it to be installed. But, when the driver is built into the kernel, you still want the build to succeed. This variable sets up a "recommends" relationship so that in the latter case, the build will not fail due to the missing package. To accomplish this, assuming the package for the module was called `kernel-module-ab123`, you would use the following in the machine's `.conf` configuration file:

```
MACHINE_ESSENTIAL_EXTRA_RRECOMMENDS += "kernel-module-ab123"
```

Some examples of these machine essentials are flash, screen, keyboard, mouse, or touchscreen drivers (depending on the machine).

MACHINE_EXTRA_RDEPENDS

A list of machine-specific packages to install as part of the image being built that are not essential for the machine to boot. However, the build process for more fully-featured images depends on the packages being present.

This variable affects all images based on `packagegroup-base`, which does not include the `core-image-minimal` or `core-image-basic` images.

The variable is similar to the `MACHINE_EXTRA_RRECOMMENDS` variable with the exception that the image being built has a build dependency on the variable's list of packages. In other words, the image will not build if a file in this list is not found.

An example is a machine that has WiFi capability but is not essential for the machine to boot the image. However, if you are building a more fully-featured image, you want to enable the WiFi. The package containing the firmware for the WiFi hardware is always expected to exist, so it is acceptable for the build process to depend upon finding the package. In this case, assuming the package for the firmware was called `wifidriver-firmware`, you would use the following in the `.conf` file for the machine:

```
MACHINE_EXTRA_RDEPENDS += "wifidriver-firmware"
```

MACHINE_EXTRA_RRECOMMENDS

A list of machine-specific packages to install as part of the image being built that are not essential for booting the machine. The image being built has no build dependency on this list of packages.

This variable affects only images based on `packagegroup-base`, which does not include the `core-image-minimal` or `core-image-basic` images.

This variable is similar to the `MACHINE_EXTRA_RDEPENDS` variable with the exception that the image being built does not have a build dependency on the variable's list of packages. In other words, the image will build if a file in this list is not found.

An example is a machine that has WiFi capability but is not essential for the machine to boot the image. However, if you are building a

more fully-featured image, you want to enable WiFi. In this case, the package containing the WiFi kernel module will not be produced if the WiFi driver is built into the kernel, in which case you still want the build to succeed instead of failing as a result of the package not being found. To accomplish this, assuming the package for the module was called `kernel-module-examplewifi`, you would use the following in the `.conf` file for the machine:

```
MACHINE_EXTRA_RRECOMMENDS += "kernel-module-examplewifi"
```

MACHINE_FEATURES Specifies the list of hardware features the MACHINE supports. For a list of features supported by the Yocto Project as shipped, see the "Machine" section.

MACHINE_FEATURES_BACKFILL Features to be added to MACHINE_FEATURES if not also present in MACHINE_FEATURES_BACKFILL_CONSIDERED.

This variable is set in the `meta/conf/bitbake.conf` file. It is not intended to be user-configurable. It is best to just reference the variable to see which machine features are being backfilled for all machine configurations. See the Feature backfilling section for more information.

MACHINE_FEATURES_BACKFILL_CONSIDERED From MACHINE_FEATURES_BACKFILL that should not be backfilled (i.e. added to MACHINE_FEATURES) during the build. See the Feature backfilling section for more information.

MAINTAINER The email address of the distribution maintainer.

MLPREFIX Specifies a prefix has been added to PN to create a special version of a recipe or package, such as a multilib version. The variable is used in places where the prefix needs to be added to or removed from a the name (e.g. the BPN variable). MLPREFIX gets set when a prefix has been added to PN.

MULTIMACH_TARGET_SYS Separates files for different machines such that you can build for multiple target machines using the same output directories. See the STAMP variable for an example.

P

P The recipe name and version. P is comprised of the following:

```
${PN} - ${PV}
```

PACKAGE_ARCH The architecture of the resulting package or packages.

PACKAGE_BEFORE_PN Enables easily adding packages to PACKAGES before `${PN}` so that the packages can pick up files that would normally be included in the default package.

PACKAGE_CLASSES This variable, which is set in the `local.conf` configuration file found in the `conf` folder of the Source Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#source-directory>], specifies the package manager to use when packaging data. You can provide one or more arguments for the variable with the first argument being the package manager used to create images:

```
PACKAGE_CLASSES ?= "package_rpm package_deb package_ipk"
```

	For information on build performance effects as a result of the package manager use, see Packaging - package*.bbclass in this manual.
PACKAGE_EXTRA_ARCHS	Specifies the list of architectures compatible with the device CPU. This variable is useful when you build for several different devices that use miscellaneous processors such as XScale and ARM926-EJS).
PACKAGECONFIG	<p>This variable provides a means of enabling or disabling features of a recipe on a per-recipe basis. The PACKAGECONFIG variable itself specifies a space-separated list of the features to enable, while the named flags set on the variable specify for each feature the additional build dependencies (DEPENDS) that should be added if the feature is enabled, and any extra arguments that should be added to the configure script argument list (EXTRA_OECONF) if the feature is enabled or disabled.</p> <p>For example, the following taken from the libsvg recipe will add --with-croco to the configure script arguments and libcroco to DEPENDS by default. However, if "croco" is removed from PACKAGECONFIG (for example, by using a .bbappend file in another layer), then --without-croco will be added to the configure script arguments instead:</p> <pre>PACKAGECONFIG ??= "croco" PACKAGECONFIG[croco] = "--with-croco,--without-croco,libcroco"</pre>
PACKAGES	<p>The list of packages to be created from the recipe. The default value is the following:</p> <pre> \${PN}-dbg \${PN}-staticdev \${PN}-dev \${PN}-doc \${PN}-locale \${PACK</pre>
PARALLEL_MAKE	Specifies extra options that are passed to the make command during the compile tasks. This variable is usually in the form -j 4, where the number represents the maximum number of parallel threads make can run. If you development host supports multiple cores a good rule of thumb is to set this variable to twice the number of cores on the host.
PF	Specifies the recipe or package name and includes all version and revision numbers (i.e. eglbc-2.13-r20+svnr15508/ and bash-4.2-r1/). This variable is comprised of the following:
	<pre> \${PN}-\${EXTENDPE}\${PV}-\${PR}</pre>
PN	<p>This variable can have two separate functions depending on the context: a recipe name or a resulting package name.</p> <p>PN refers to a recipe name in the context of a file used by the OpenEmbedded build system as input to create a package. The name is normally extracted from the recipe file name. For example, if the recipe is named expat_2.0.1.bb, then the default value of PN will be "expat".</p> <p>The variable refers to a package name in the context of a file created or produced by the OpenEmbedded build system.</p> <p>If applicable, the PN variable also contains any special suffix or prefix. For example, using bash to build packages for the native machine,</p>

- PN is bash-native. Using bash to build packages for the target and for Multilib, PN would be bash and lib64-bash, respectively.
- PR** The revision of the recipe. The default value for this variable is "r0".
- PRINC** Causes the PR variable of .bbappend files to dynamically increment. This increment minimizes the impact of layer ordering.
- In order to ensure multiple .bbappend files can co-exist, PRINC should be self referencing. This variable defaults to 0.
- Following is an example that increments PR by two:
- ```
PRINC := "${@int(PRINC) + 2}"
```
- It is advisable not to use strings such as ".= '1'" with the variable because this usage is very sensitive to layer ordering. Explicit assignments should be avoided as they cannot adequately represent multiple .bbappend files.
- PV** The version of the recipe. The version is normally extracted from the recipe filename. For example, if the recipe is named expat\_2.0.1.bb, then the default value of PV will be "2.0.1". PV is generally not overridden within a recipe unless it is building an unstable (i.e. development) version from a source code repository (e.g. Git or Subversion).
- PE** the epoch of the recipe. The default value is "0". The field is used to make upgrades possible when the versioning scheme changes in some backwards incompatible way.
- PREFERRED\_PROVIDER** If multiple recipes provide an item, this variable determines which recipe should be given preference. The variable must always be suffixed with the name of the provided item, and should be set to the PN of the recipe to which you want to give precedence. Here is an example:
- ```
PREFERRED_PROVIDER_virtual/xserver = "xserver-xf86"
```
- PREFERRED_VERSION** If there are multiple versions of recipes available, this variable determines which recipe should be given preference. The variable must always be suffixed with the PN for which to select, and should be set to the PV to which you want to give precedence. You can use the "%" character as a wildcard to match any number of characters, which can be useful when specifying versions that contain long revision number that could potentially change. Here are two examples:

```
PREFERRED_VERSION_python = "2.6.6"  
PREFERRED_VERSION_linux-yocto = "3.0+git%"
```

R

- RCONFLICTS** The list of packages that conflict with a package. Note that the package will not be installed if the conflicting packages are not first removed.
- Like all package-controlling variables, you must always use them in conjunction with a package name override. Here is an example:

```
RCONFLICTS_${PN} = "another-conflicting-package-name"
```

RDEPENDS

Lists a package's run-time dependencies (i.e. other packages) that must be installed for the package to be built. In other words, in order for the package to be built and run correctly, it depends on the listed packages. If a package in this list cannot be found, it is probable that a dependency error would occur before the build.

The names of the variables you list with RDEPENDS must be the names of other packages as listed in the PACKAGES variable. You should not list recipe names (PN).

Because the RDEPENDS variable applies to packages being built, you should always attach a package name to the variable to specify the particular run-time package that has the dependency. For example, suppose you are building a development package that depends on the perl package. In this case, you would use the following RDEPENDS statement:

```
RDEPENDS_${PN}-dev += "perl"
```

In the example, the package name (\${PN}-dev) must appear as it would in the PACKAGES namespace before any renaming of the output package by classes like `debian.bbclass`.

In many cases you do not need to explicitly add dependencies to RDEPENDS since some automatic handling occurs:

- `shlibdeps`: If a run-time package contains a shared library (`.so`), the build processes the library in order to determine other libraries to which it is dynamically linked. The build process adds these libraries to RDEPENDS when creating the run-time package.
- `pcdeps`: If the package ships a `pkg-config` information file, the build process uses this file to add items to the RDEPENDS variable to create the run-time packages.

RRECOMMENDS

A list of packages that extend the usability of a package being built. The package being built does not depend on this list of packages in order to successfully build, but needs them for the extended usability. To specify runtime dependencies for packages, see the RDEPENDS variable.

The OpenEmbedded build process automatically installs the list of packages as part of the built package. However, you can remove them later if you want. If, during the build, a package from the list cannot be found, the build process continues without an error.

Because the RRECOMMENDS variable applies to packages being built, you should always attach an override to the variable to specify the particular package whose usability is being extended. For example, suppose you are building a development package that is extended to support wireless functionality. In this case, you would use the following:

```
RRECOMMENDS_${PN}-dev += "<wireless_package_name>"
```

In the example, the package name (\${PN}-dev) must appear as it would in the PACKAGES namespace before any renaming of the output package by classes like `debian.bbclass`.

RREPLACES

The list of packages that are replaced with this package.

S

S	<p>The location in the Build Directory [http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#build-directory] where unpacked package source code resides. This location is within the working directory (WORKDIR), which is not static. The unpacked source location depends on the package name (PN) and package version (PV) as follows:</p> <pre style="text-align: center;">\${WORKDIR}/\${PN} - \${PV}</pre> <p>As an example, assume a Source Directory [http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#source-directory] top-level folder named poky and a default Build Directory [http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#build-directory] at poky/build. In this case, the working directory the build system uses to build the db package is the following:</p> <pre style="text-align: center;">~/poky/build/tmp/work/qemux86-poky-linux/db-5.1.19-r3/db-5.1.19</pre>
SDKIMAGE_FEATURES	Equivalent to IMAGE_FEATURES. However, this variable applies to the SDK generated from an image using <code>bitbake -c populate_sdk imagename</code>).
SECTION	The section in which packages should be categorized. Package management utilities can make use of this variable.
SELECTED_OPTIMIZATION	The variable takes the value of FULL_OPTIMIZATION unless <code>DEBUG_BUILD = "1"</code> . In this case the value of <code>DEBUG_OPTIMIZATION</code> is used.
SERIAL_CONSOLE	The speed and device for the serial port used to attach the serial console. This variable is given to the kernel as the "console" parameter and after booting occurs <code>getty</code> is started on that port so remote login is possible.
SITEINFO_ENDIANNES	Specifies the endian byte order of the target system. The value should be either "le" for little-endian or "be" for big-endian.
SITEINFO_BITS	Specifies the number of bits for the target system CPU. The value should be either "32" or "64".
SPECIAL_PKGSUFFIX	A list of prefixes for PN used by the OpenEmbedded build system to create variants of recipes or packages. The list specifies the prefixes to strip off during certain circumstances such as the generation of the BPN variable.
SRC_URI	<p>The list of source files - local or remote. This variable tells the OpenEmbedded build system which bits to pull in for the build and how to pull them in. For example, if the recipe only needs to fetch a tarball from the internet, the recipe uses a single SRC_URI entry. On the other hand, if the recipe needs to fetch a tarball, apply two patches, and include a custom file, the recipe would include four instances of the variable.</p> <p>The following list explains the available URI protocols:</p> <ul style="list-style-type: none"> • <code>file://</code> - Fetches files, which is usually a file shipped with the metadata, from the local machine. The path is relative to the FILESPATH variable. Thus, the build system searches, in order, from the following directories, which are assumed to be a subdirectories of the directory in which the recipe file resides:

- `${PN}` - The recipe name with any special suffix or prefix, if applicable. For example, using bash to build for the native machine, PN is bash-native. Using bash to build for the target and for Multilib, PN would be bash and lib64-bash, respectively.
- `${PF}` - `${PN}-${EXTENDPE}${PV}-${PR}`. The recipe name including all version and revision numbers (i.e. eglibc-2.13-r20+svnr15508/ and bash-4.2-r1/).
- `${P}` - `${PN}-${PV}`. The recipe name and version (i.e. bash-4.2).
- `${BPN}` - The base recipe name without any special suffix or version numbers.
- `${BP}` - `${BPN}-${PV}`. The base recipe name and version but without any special package name suffix.
- Files - Files beneath the directory in which the recipe resides.
- Directory - The directory itself in which the recipe resides.
- `bzr://` - Fetches files from a Bazaar revision control repository.
- `git://` - Fetches files from a Git revision control repository.
- `osc://` - Fetches files from an OSC (OpenSuse Build service) revision control repository.
- `repo://` - Fetches files from a repo (Git) repository.
- `svk://` - Fetches files from an SVK revision control repository.
- `http://` - Fetches files from the Internet using http.
- `https://` - Fetches files from the Internet using https.
- `ftp://` - Fetches files from the Internet using ftp.
- `cvs://` - Fetches files from a CVS revision control repository.
- `hg://` - Fetches files from a Mercurial (hg) revision control repository.
- `p4://` - Fetches files from a Perforce (p4) revision control repository.
- `ssh://` - Fetches files from a secure shell.
- `svn://` - Fetches files from a Subversion (svn) revision control repository.

Standard and recipe-specific options for SRC_URI exist. Here are standard options:

- `apply` - Whether to apply the patch or not. The default action is to apply the patch.
- `striplevel` - Which striplevel to use when applying the patch. The default level is 1.

Here are options specific to recipes building code from a revision control system:

- `mindate` - Only applies the patch if SRCDATE is equal to or greater than mindate.

- `maxdate` - Only applies the patch if `SRCDATE` is not later than `mindate`.
- `minrev` - Only applies the patch if `SRCREV` is equal to or greater than `minrev`.
- `maxrev` - Only applies the patch if `SRCREV` is not later than `maxrev`.
- `rev` - Only applies the patch if `SRCREV` is equal to `rev`.
- `not rev` - Only applies the patch if `SRCREV` is not equal to `rev`.

Here are some additional options worth mentioning:

- `unpack` - Controls whether or not to unpack the file if it is an archive. The default action is to upack the file.
- `subdir` - Places the file (or extracts its contents) into the specified subdirectory of `WORKDIR`. This option is useful for unusual tarballs or other archives that don't have their files already in a subdirectory within the archive.
- `name` - Specifies a name to be used for association with `SRC_URI` checksums when you have more than one file specified in `SRC_URI`.
- `downloadfilename` - Specifies the filename used when storing the downloaded file.

`SRC_URI_OVERRIDES_PACKAGE_ARCH`

By default, the OpenEmbedded build system automatically detects whether `SRC_URI` contains files that are machine-specific. If so, the build system automatically changes `PACKAGE_ARCH`. Setting this variable to "0" disables this behavior.

`SRCDATE`

The date of the source code used to build the package. This variable applies only if the source was fetched from a Source Code Manager (SCM).

`SRCREV`

The revision of the source code used to build the package. This variable applies to Subversion, Git, Mercurial and Bazaar only. Note that if you wish to build a fixed revision and you wish to avoid performing a query on the remote repository every time BitBake parses your recipe, you should specify a `SRCREV` that is a full revision identifier and not just a tag.

`SSTATE_DIR`

The directory for the shared state.

`SSTATE_MIRRORS`

Configures the OpenEmbedded build system to search other mirror locations for prebuilt cache data objects before building out the data. This variable works like fetcher `MIRRORS/PREMIRRORS` and points to the cache locations to check for the shared objects.

You can specify a filesystem directory or a remote URL such as HTTP or FTP. The locations you specify need to contain the shared state cache (`sstate-cache`) results from previous builds. The `sstate-cache` you point to can also be from builds on other machines.

If a mirror uses the same structure as `SSTATE_DIR`, you need to add "PATH" at the end as shown in the examples below. The build system substitutes the correct path within the directory structure.

```
SSTATE_MIRRORS ?= "\
file://.* http://someserver.tld/share/sstate/PATH \n \
file://.* file:///some/local/dir/sstate/PATH"
```

STAGING_KERNEL_DIR The directory with kernel headers that are required to build out-of-tree modules.

STAMP Specifies the base path used to create recipe stamp files. The path to an actual stamp file is constructed by evaluating this string and then appending additional information. Currently, the default assignment for STAMP as set in the meta/conf/bitbake.conf file is:

```
STAMP = "${TMPDIR}/stamps/${MULTIMACH_TARGET_SYS}/${PN}-${EXTENDP
```

See TMPDIR, MULTIMACH_TARGET_SYS, PN, EXTENDPE, PV, and PR for related variable information.

SUMMARY The short (72 characters or less) summary of the binary package for packaging systems such as opkg, rpm or dpkg. By default, SUMMARY is used to define the DESCRIPTION variable if DESCRIPTION is not set in the recipe.

T

T This variable points to a directory where Bitbake places temporary files when building a particular package. It is typically set as follows:

```
T = ${WORKDIR}/temp
```

The WORKDIR is the directory into which Bitbake unpacks and builds the package. The default bitbake.conf file sets this variable.

The T variable is not to be confused with the TMPDIR variable, which points to the root of the directory tree where Bitbake places the output of an entire build.

TARGET_ARCH The architecture of the device being built. While a number of values are possible, the OpenEmbedded build system primarily supports arm and i586.

TARGET_CFLAGS Flags passed to the C compiler for the target system. This variable evaluates to the same as CFLAGS.

TARGET_FPU Specifies the method for handling FPU code. For FPU-less targets, which include most ARM CPUs, the variable must be set to "soft". If not, the kernel emulation gets used, which results in a performance penalty.

TARGET_OS Specifies the target's operating system. The variable can be set to "linux" for glibc-based systems and to "linux-uclibc" for uclibc. For ARM/EABI targets, there are also "linux-gnueabi" and "linux-uclibc-gnueabi" values possible.

TCLIBC Specifies which variant of the GNU standard C library (libc) to use during the build process. This variable replaces POKYLIBC, which is no longer supported.

You can select eglibc or uclibc.

Note

This release of the Yocto Project does not support the glibc implementation of libc.

TCMODE The toolchain selector. This variable replaces POKYMODE, which is no longer supported.

The `TCMODE` variable selects the external toolchain built using the OpenEmbedded build system or a few supported combinations of the upstream GCC or CodeSourcery Labs toolchain. The variable identifies the `tcmode-*` files used in the `meta/conf/distro/include` directory, which is found in the Source Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#source-directory>].

By default, `TCMODE` is set to "default", which chooses the `tcmode-default.inc` file. The variable is similar to `TCLIBC`, which controls the variant of the GNU standard C library (`libc`) used during the build process: `eglibc` or `uclibc`.

TMPDIR

This variable is the temporary directory the OpenEmbedded build system uses when it does its work building images. By default, the `TMPDIR` variable is named `tmp` within the Build Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#build-directory>].

If you want to establish this directory in a location other than the default, you can uncomment the following statement in the `conf/local.conf` file in the Source Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#source-directory>]:

```
#TMPDIR = "${TOPDIR}/tmp"
```

TOPDIR

This variable is the Build Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#build-directory>]. BitBake automatically sets this variable. The OpenEmbedded build system uses the Build Directory when building images.

W**WORKDIR**

The pathname of the working directory in which the OpenEmbedded build system builds a recipe. This directory is located within the `TMPDIR` directory structure and changes as different packages are built.

The actual `WORKDIR` directory depends on several things:

- The temporary directory - `TMPDIR`
- The package architecture - `PACKAGE_ARCH`
- The target machine - `MACHINE`
- The target operating system - `TARGET_OS`
- The recipe name - `PN`
- The recipe version - `PV`
- The recipe revision - `PR`

For packages that are not dependent on a particular machine, `WORKDIR` is defined as follows:

```
${TMPDIR}/work/${PACKAGE_ARCH}-poky-${TARGET_OS}/${PN}-${PV}-${PR}
```

As an example, assume a Source Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev->

manual.html#source-directory] top-level folder name poky and a default Build Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#build-directory>] at poky/build. In this case, the working directory the build system uses to build the v86d package is the following:

```
~/poky/build/tmp/work/qemux86-poky-linux/v86d-01.9-r0
```

For packages that are dependent on a particular machine, WORKDIR is defined slightly different:

```
${TMPDIR}/work/${MACHINE}-poky-${TARGET_OS}/${PN}-${PV}-${PR}
```

As an example, again assume a Source Directory top-level folder named poky and a default Build Directory at poky/build. In this case, the working directory the build system uses to build the acl recipe, which is being built for a MIPS-based device, is the following:

```
~/poky/build/tmp/work/mips-poky-linux/acl-2.2.51-r2
```

Chapter 11. Variable Context

While most variables can be used in almost any context such as `.conf`, `.bbclass`, `.inc`, and `.bb` files, some variables are often associated with a particular locality or context. This chapter describes some common associations.

11.1. Configuration

The following subsections provide lists of variables whose context is configuration: distribution, machine, and local.

11.1.1. Distribution (Distro)

This section lists variables whose context is the distribution, or distro.

- DISTRO
- DISTRO_NAME
- DISTRO_VERSION
- MAINTAINER
- PACKAGE_CLASSES
- TARGET_OS
- TARGET_FPU
- TCMODE
- TCLIBC

11.1.2. Machine

This section lists variables whose context is the machine.

- TARGET_ARCH
- SERIAL_CONSOLE
- PACKAGE_EXTRA_ARCHS
- IMAGE_FSTYPES
- MACHINE_FEATURES
- MACHINE_EXTRA_RDEPENDS
- MACHINE_EXTRA_RRECOMMENDS
- MACHINE_ESSENTIAL_EXTRA_RDEPENDS
- MACHINE_ESSENTIAL_EXTRA_RRECOMMENDS

11.1.3. Local

This section lists variables whose context is the local configuration through the `local.conf` file.

- DISTRO
- MACHINE
- DL_DIR

- BBFILES
- EXTRA_IMAGE_FEATURES
- PACKAGE_CLASSES
- BB_NUMBER_THREADS
- BBINCLUDELOGS
- ENABLE_BINARY_LOCALE_GENERATION

11.2. Recipes

The following subsections provide lists of variables whose context is recipes: required, dependencies, path, and extra build information.

11.2.1. Required

This section lists variables that are required for recipes.

- LICENSE
- LIC_FILES_CHKSUM
- SRC_URI - used in recipes that fetch local or remote files.

11.2.2. Dependencies

This section lists variables that define recipe dependencies.

- DEPENDS
- RDEPENDS
- RRECOMMENDS
- RCONFLICTS
- RREPLACES

11.2.3. Paths

This section lists variables that define recipe paths.

- WORKDIR
- S
- FILES

11.2.4. Extra Build Information

This section lists variables that define extra build information for recipes.

- EXTRA_OECMAKE
- EXTRA_OECONF
- EXTRA_OEMAKE
- PACKAGES
- DEFAULT_PREFERENCE

Chapter 12. FAQ

12.1. How does Poky differ from OpenEmbedded [<http://www.openembedded.org>]?

The term "Poky" refers to the specific reference build system that the Yocto Project provides. Poky is based on OE-Core [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#oe-core>] and BitBake. Thus, the generic term used here for the build system is the "OpenEmbedded build system." Development in the Yocto Project using Poky is closely tied to OpenEmbedded, with changes always being merged to OE-Core or BitBake first before being pulled back into Poky. This practice benefits both projects immediately. For a fuller description of the term "Poky", see the poky [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#poky>] term in the Yocto Project Development Manual.

12.2. I only have Python 2.4 or 2.5 but BitBake requires Python 2.6 or 2.7. Can I still use the Yocto Project?

You can use a stand-alone tarball to provide Python 2.6. You can find pre-built 32 and 64-bit versions of Python 2.6 at the following locations:

- 32-bit tarball [<http://downloads.yoctoproject.org/releases/miscsupport/python-nativesdk-standalone-i686.tar.bz2>]
- 64-bit tarball [http://downloads.yoctoproject.org/releases/miscsupport/python-nativesdk-standalone-x86_64.tar.bz2]

These tarballs are self-contained with all required libraries and should work on most Linux systems. To use the tarballs extract them into the root directory and run the appropriate command:

```
$ export PATH=/opt/poky/sysroots/i586-pokysdk-linux/usr/bin/:$PATH
$ export PATH=/opt/poky/sysroots/x86_64-pokysdk-linux/usr/bin/:$PATH
```

Once you run the command, BitBake uses Python 2.6.

12.3. How can you claim Poky / OpenEmbedded-Core is stable?

There are three areas that help with stability;

- The Yocto Project team keeps OE-Core [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#oe-core>] small and focused, containing around 830 recipes as opposed to the thousands available in other OpenEmbedded community layers. Keeping it small makes it easy to test and maintain.
- The Yocto Project team runs manual and automated tests using a small, fixed set of reference hardware as well as emulated targets.
- The Yocto Project uses an an autobuilder, which provides continuous build and integration tests.

12.4. How do I get support for my board added to the Yocto Project?

Support for an additional board is added by creating a BSP layer for it. For more information on how to create a BSP layer, see the Yocto Project Board Support Package (BSP) Developer's Guide [<http://www.yoctoproject.org/docs/1.3/bsp-guide/bsp-guide.html>].

Usually, if the board is not completely exotic, adding support in the Yocto Project is fairly straightforward.

12.5. Are there any products built using the OpenEmbedded build system?

The software running on the Vernier LabQuest [<http://vernier.com/labquest/>] is built using the OpenEmbedded build system. See the Vernier LabQuest [<http://www.vernier.com/products/interfaces/labq/>] website for more information. There are a number of pre-production devices

using the OpenEmbedded build system and the Yocto Project team announces them as soon as they are released.

12.6. What does the OpenEmbedded build system produce as output?

Because the same set of recipes can be used to create output of various formats, the output of an OpenEmbedded build depends on how it was started. Usually, the output is a flashable image ready for the target device.

12.7. How do I add my package to the Yocto Project?

To add a package, you need to create a BitBake recipe. For information on how to add a package, see the section "Adding a Package [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#usingpokyo-extend-addpkg>]" in the Yocto Project Development Manual.

12.8. Do I have to reflash my entire board with a new Yocto Project image when recompiling a package?

The OpenEmbedded build system can build packages in various formats such as ipk for opkg, Debian package (.deb), or RPM. The packages can then be upgraded using the package tools on the device, much like on a desktop distribution such as Ubuntu or Fedora.

12.9. What is GNOME Mobile and what is the difference between GNOME Mobile and GNOME?

GNOME Mobile is a subset of the GNOME [<http://www.gnome.org>] platform targeted at mobile and embedded devices. The the main difference between GNOME Mobile and standard GNOME is that desktop-orientated libraries have been removed, along with deprecated libraries, creating a much smaller footprint.

12.10. I see the error 'chmod: XXXXX new permissions are r-xrwxrwx, not r-xr-xr-x'. What is wrong?

You are probably running the build on an NTFS filesystem. Use ext2, ext3, or ext4 instead.

12.11. How do I make the Yocto Project work in RHEL/CentOS?

To get the Yocto Project working under RHEL/CentOS 5.1 you need to first install some required packages. The standard CentOS packages needed are:

- "Development tools" (selected during installation)
- texi2html
- compat-gcc-34

On top of these, you need the following external packages:

- python-sqlite2 from DAG repository [<http://dag.wieers.com/rpm/packages/python-sqlite2/>]
- help2man from Karan repository [http://centos.karan.org/el4/extras/stable/x86_64/RPMS/repodata/repoview/help2man-0-1.33.1-2.html]

Once these packages are installed, the OpenEmbedded build system will be able to build standard images. However, there might be a problem with the QEMU emulator segfaulting. You can either disable the generation of binary locales by setting `ENABLE_BINARY_LOCALE_GENERATION` to "0" or by removing the `linux-2.6-execshield.patch` from the kernel and rebuilding it since that is the patch that causes the problems with QEMU.

12.12. I see lots of 404 responses for files on <http://www.yoctoproject.org/sources/> *. Is something wrong?

Nothing is wrong. The OpenEmbedded build system checks any configured source mirrors before downloading from the upstream sources. The build system does this searching for both source archives and pre-checked out versions of SCM managed software. These checks help in large installations because it can reduce load on the SCM servers themselves. The address above is one of the default mirrors configured into the build system. Consequently, if an upstream source disappears, the team can place sources there so builds continue to work.

12.13 I have machine-specific data in a package for one machine only but the package is being marked as machine-specific in all cases, how do I prevent this?

Set `SRC_URI_OVERRIDES_PACKAGE_ARCH = "0"` in the `.bb` file but make sure the package is manually marked as machine-specific in the case that needs it. The code that handles `SRC_URI_OVERRIDES_PACKAGE_ARCH` is in `base.bbclass`.

12.14 I'm behind a firewall and need to use a proxy server. How do I do that?

Most source fetching by the OpenEmbedded build system is done by `wget` and you therefore need to specify the proxy settings in a `.wgetrc` file in your home directory. Example settings in that file would be

```
http_proxy = http://proxy.yoyodyne.com:18023/  
ftp_proxy = http://proxy.yoyodyne.com:18023/
```

The Yocto Project also includes a `site.conf.sample` file that shows how to configure CVS and Git proxy servers if needed.

12.15 What's the difference between `foo` and `foo-native`?

The `*-native` targets are designed to run on the system being used for the build. These are usually tools that are needed to assist the build in some way such as `quilt-native`, which is used to apply patches. The non-native version is the one that runs on the target device.

12.16 I'm seeing random build failures. Help?!

If the same build is failing in totally different and random ways, the most likely explanation is that either the hardware you're running the build on has some problem, or, if you are running the build under virtualisation, the virtualisation probably has bugs. The OpenEmbedded build system processes a massive amount of data causing lots of network, disk and CPU activity and is sensitive to even single bit failures in any of these areas. True random failures have always been traced back to hardware or virtualisation issues.

12.17 What do we need to ship for license compliance?

This is a difficult question and you need to consult your lawyer for the answer for your specific case. It is worth bearing in mind that for GPL compliance there needs to be enough information shipped to allow someone else to rebuild the same end result you are shipping. This means sharing the source code, any patches applied to it, and also any configuration information about how that package was configured and built.

12.18 How do I disable the cursor on my touchscreen device?

You need to create a form factor file as described in the "Miscellaneous Recipe Files [<http://www.yoctoproject.org/docs/1.3/bsp-guide/bsp-guide.html#bsp-filelayout-misc-recipes>]" section and set the `HAVE_TOUCHSCREEN` variable equal to one as follows:

```
HAVE_TOUCHSCREEN=1
```

12.19 How do I make sure connected network interfaces are brought up by default?

The default interfaces file provided by the `netbase` recipe does not automatically bring up network interfaces. Therefore, you will need to add a BSP-specific `netbase` that includes an interfaces file. See the "Miscellaneous Recipe Files [<http://www.yoctoproject.org/docs/1.3/bsp-guide/bsp-guide.html#bsp-filelayout-misc-recipes>]" section for information on creating these types of miscellaneous recipe files.

For example, add the following files to your layer:

```
meta-MACHINE/recipes-bsp/netbase/netbase/MACHINE/interfaces  
meta-MACHINE/recipes-bsp/netbase/netbase_5.0.bbappend
```

12.20. How do I create images with more free space?

Images are created to be 1.2 times the size of the populated root filesystem. To modify this ratio so that there is more free space available, you need to set the configuration value `IMAGE_OVERHEAD_FACTOR`. For example, setting `IMAGE_OVERHEAD_FACTOR` to 1.5 sets the image size ratio to one and a half times the size of the populated root filesystem.

```
IMAGE_OVERHEAD_FACTOR = "1.5"
```

12.21. Why don't you support directories with spaces in the pathnames?

The Yocto Project team has tried to do this before but too many of the tools the OpenEmbedded build system depends on such as `autoconf` break when they find spaces in pathnames. Until that situation changes, the team will not support spaces in pathnames.

12.22. How do I use an external toolchain?

The toolchain configuration is very flexible and customizable. It is primarily controlled with the `TCMODE` variable. This variable controls which `tcmode-*.inc` file to include from the `meta/conf/distro/include` directory within the source directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#source-directory>].

The default value of `TCMODE` is "default" (i.e. `tcmode-default.inc`). However, other patterns are accepted. In particular, "external-*" refers to external toolchains of which there are some basic examples included in the OpenEmbedded Core (meta). You can use your own custom toolchain definition in your own layer (or as defined in the `local.conf` file) at the location `conf/distro/include/tcmode-*.inc`.

In addition to the toolchain configuration, you also need a corresponding toolchain recipe file. This recipe file needs to package up any pre-built objects in the toolchain such as `libgcc`, `libstdc++`, any locales, and `libc`. An example is the `external-sourcery-toolchain.bb`, which is located in `meta/recipes-core/meta/` within the source directory.

12.23. How does the OpenEmbedded build system obtain source code and will it work behind my firewall or proxy server?

The way the build system obtains source code is highly configurable. You can setup the build system to get source code in most environments if HTTP transport is available.

When the build system searches for source code, it first tries the local download directory. If that location fails, Poky tries `PREMIRRORS`, the upstream source, and then `MIRRORS` in that order.

By default, the OpenEmbedded build system uses the Yocto Project source `PREMIRRORS` for SCM-based sources, upstreams for normal tarballs, and then falls back to a number of other mirrors including the Yocto Project source mirror if those fail.

As an example, you could add a specific server for Poky to attempt before any others by adding something like the following to the `local.conf` configuration file:

```
PREMIRRORS_prepend = "\
git://.*/* http://www.yoctoproject.org/sources/ \n \
ftp://.*/* http://www.yoctoproject.org/sources/ \n \
http://.*/* http://www.yoctoproject.org/sources/ \n \
https://.*/* http://www.yoctoproject.org/sources/ \n"
```

These changes cause Poky to intercept Git, FTP, HTTP, and HTTPS requests and direct them to the `http://sources` mirror. You can use `file://` URLs to point to local directories or network shares as well.

Aside from the previous technique, these options also exist:

```
BB_NO_NETWORK = "1"
```

This statement tells BitBake to throw an error instead of trying to access the Internet. This technique is useful if you want to ensure code builds only from local sources.

Here is another technique:

```
BB_FETCH_PREMIRRORONLY = "1"
```

This statement limits Poky to pulling source from the PREMIRRORS only. Again, this technique is useful for reproducing builds.

Here is another technique:

```
BB_GENERATE_MIRROR_TARBALLS = "1"
```

This statement tells Poky to generate mirror tarballs. This technique is useful if you want to create a mirror server. If not, however, the technique can simply waste time during the build.

Finally, consider an example where you are behind an HTTP-only firewall. You could make the following changes to the `local.conf` configuration file as long as the PREMIRROR server is up to date:

```
PREMIRRORS_prepend = "\n\
ftp://.*/.* http://www.yoctoproject.org/sources/ \n \
http://.*/.* http://www.yoctoproject.org/sources/ \n \
https://.*/.* http://www.yoctoproject.org/sources/ \n"
BB_FETCH_PREMIRRORONLY = "1"
```

These changes would cause Poky to successfully fetch source over HTTP and any network accesses to anything other than the PREMIRROR would fail.

The build system also honors the standard shell environment variables `http_proxy`, `ftp_proxy`, `https_proxy`, and `all_proxy` to redirect requests through proxy servers.

12.24. Can I get rid of build output so I can start over?

Yes - you can easily do this. When you use BitBake to build an image, all the build output goes into the directory created when you source the `oe-init-build-env` setup file. By default, this build directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#build-directory>] is named `build` but can be named anything you want.

Within the build directory is the `tmp` directory. To remove all the build output yet preserve any source code or downloaded files from previous builds, simply remove the `tmp` directory.

Chapter 13. Contributing to the Yocto Project

13.1. Introduction

The Yocto Project team is happy for people to experiment with the Yocto Project. A number of places exist to find help if you run into difficulties or find bugs. To find out how to download source code, see the "Yocto Project Release [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#local-yp-release>]" list item in the Yocto Project Development Manual.

13.2. Tracking Bugs

If you find problems with the Yocto Project, you should report them using the Bugzilla application at <http://bugzilla.yoctoproject.org>.

13.3. Mailing lists

There are a number of mailing lists maintained by the Yocto Project as well as related OpenEmbedded mailing lists for discussion, patch submission and announcements. To subscribe to one of the following mailing lists, click on the appropriate URL in the following list and follow the instructions:

- <http://lists.yoctoproject.org/listinfo/yocto> - General Yocto Project discussion mailing list.
- <http://lists.linuxtogo.org/cgi-bin/mailman/listinfo/openembedded-core> - Discussion mailing list about OpenEmbedded-Core (the core metadata).
- <http://lists.linuxtogo.org/cgi-bin/mailman/listinfo/openembedded-devel> - Discussion mailing list about OpenEmbedded.
- <http://lists.linuxtogo.org/cgi-bin/mailman/listinfo/bitbake-devel> - Discussion mailing list about the BitBake build tool.
- <http://lists.yoctoproject.org/listinfo/poky> - Discussion mailing list about Poky.
- <http://lists.yoctoproject.org/listinfo/yocto-announce> - Mailing list to receive official Yocto Project release and milestone announcements.

13.4. Internet Relay Chat (IRC)

Two IRC channels on freenode are available for the Yocto Project and Poky discussions:

- #yocto
- #poky

13.5. Links

Following is a list of resources you will find helpful:

- The Yocto Project website [<http://www.yoctoproject.org>]: The home site for the Yocto Project.
- Intel Corporation [<http://www.intel.com/>]: The company who acquired OpenedHand in 2008 and began development on the Yocto Project.
- OpenEmbedded [<http://www.openembedded.org>]: The upstream, generic, embedded distribution used as the basis for the build system in the Yocto Project. Poky derives from and contributes back to the OpenEmbedded project.
- BitBake [<http://developer.berlios.de/projects/bitbake/>]: The tool used to process metadata.

- BitBake User Manual: A comprehensive guide to the BitBake tool. You can find the BitBake User Manual in the `bitbake/doc/manual` directory, which is found in the Source Directory [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#source-directory>].
- QEMU [<http://wiki.qemu.org/Index.html>]: An open source machine emulator and virtualizer.

13.6. Contributions

The Yocto Project gladly accepts contributions. You can submit changes to the project either by creating and sending pull requests, or by submitting patches through email. For information on how to do both, see the "How to Submit a Change [<http://www.yoctoproject.org/docs/1.3/dev-manual/dev-manual.html#how-to-submit-a-change>]" section in the Yocto Project Development Manual.